

# Spectrum™ Technology Platform

Version 12.0 SP1

## Installation Guide

Windows



# Table of Contents

## 1 - Planning Your Installation

---

Installation Scenarios	5
System Requirements	8

## 2 - Standard Installation

---

Installing a New Server	22
Upgrading a Server	23
Installing a License Key	27
Installing the Server with a Silent Installer	28
Adding Modules	28
Removing the Server	29

## 3 - Cluster

---

Clustered Architecture	32
Requirements	36
Installing a Cluster	36
Installing a Cluster for the Location Intelligence Module	42
Upgrading a Cluster	47
Upgrading a Cluster with the Data Hub Module	48
Upgrading a Cluster with the Location Intelligence Module	51
Removing a Node from a Cluster	53
Adding Modules to a Cluster	54
Starting a Cluster	55
Stopping a Cluster	56
Using Enterprise Designer with a Cluster	56

## 4 - Cluster with Separated Configuration Database

---

Installing a Cluster with a Separated Configuration Database	58
Upgrading a Cluster with a Separated Database	63
Upgrading a Cluster with a Separated Database and Data Hub Module	66
Converting to a Separated Configuration Database	70
Converting from a Separated Configuration Database to a Standard Installation	72
Adding Modules to a Cluster	74

## 5 - Spectrum Databases

---

Installing a Spectrum Database	76
Installing the Address Now Module Database	77
Installing the Advanced Matching Module Database	77
Installing Data Normalization Module Databases	78
Installing Enterprise Geocoding Module Databases	80
Installing Enterprise Routing Module Databases	83
Installing Enterprise Tax Module Databases	83
Installing GeoEnrichment Module Databases	87
Installing Global Addressing Module Databases	88
Installing Global Geocoding Module Databases	90
Installing the Global Sentry Module Database	93
Installing Location Intelligence Module Databases	95
Installing Universal Addressing Module Databases	96

Installing Universal Name Module Databases	98
Using the Database Silent Installer	99

## 6 - Client Tools

---

Installing the Client Tools	102
Installing Enterprise Designer with a Silent Installer	103
Upgrading Enterprise Designer	104
Removing Enterprise Designer	105

## 7 - Client API

---

Installing the Client API	107
Removing the Client API	107

## 8 - SAP, Siebel, SugarCRM, and Microsoft Dynamics

---

Configuring SAP	109
Configuring Siebel	117
Configuring SugarCRM	164
Configuring Microsoft Dynamics CRM	168

## 9 - Support

---

Support	173
---------	-----

# 1 - Planning Your Installation

## In this section

---


Installation Scenarios	5
System Requirements	8

## Installation Scenarios

Spectrum™ Technology Platform supports a variety of installation scenarios that scale to fit the needs of your organization.

### Standard


The standard scenario is the simplest installation scenario. You install Spectrum™ Technology Platform on a single server. All activity is handled by this one server, including designing dataflows, storage of configuration information, running jobs, and handling service requests.



### Remote Servers

Remote servers are useful if you have licensed many modules. To use remote servers, you install Spectrum™ Technology Platform on several different servers, installing different modules on each server. You then configure the individual services to execute on one of the remote servers. This approach has the following advantages:


- Improved performance, especially for web service and API calls. For jobs, there may be some performance improvement, but the time it takes to send data across the network to the remote server may offset any performance gains.
- Ability to perform database updates on individual modules without interrupting the availability of other modules. For example, if you need to update a postal database for the Universal Addressing Module, you could install the update by stopping just the remote server handling the Universal Addressing Module, allowing other modules to remain available on other remote servers.
- Startup time can be reduced. With all modules on one server, it can take a long time for the server to start up. With modules installed on separate servers, each server will start up more quickly.



**Cluster**

In a clustered environment, processing is shared among two or more instances of the server. All communication with Spectrum™ Technology Platform goes through a load balancer. Instead of using the URL and port of the Spectrum™ Technology Platform server, you use the URL and port of the load balancer. Consider using this approach if you require failover redundancy and high-volume, high-performance processing.

This diagram illustrates the cluster architecture:



This approach has the following advantages:

- Processing is automatically distributed among the nodes in the cluster for optimal performance.
- Configuration settings are automatically synchronized across nodes.
- Uptime can be improved since if a node goes down the other nodes remain available to handle processing requests.
- Adding a new node is easy.

### *Cluster with Separated Configuration Database*


When you install the Spectrum™ Technology Platform server you are installing two things: server software and a configuration database. The server handles the execution of jobs and service requests, reporting, and logging. The configuration database stores data such as users and roles, data connections, dataflows, and the audit log.

For clusters consisting of only a few nodes, installing the server and configuration database together on the same server provides acceptable performance. However, a cluster that consists of a large number of nodes may have its performance negatively affected by having a copy of the configuration database on each node. This is because an increasing number of nodes results in increased data replication between nodes during synchronization. Performance may also suffer if users are accessing the configuration database frequently through activities such as editing dataflows or job schedules. These activities require processing power, resulting in less CPU capacity available for running jobs and responding to service requests.

If you have an implementation with four or more nodes, you should consider installing the configuration database to separate servers. This is the most scalable installation scenario because you can add nodes without necessarily adding another instance of the configuration database. For example, say you have five nodes and three configuration database servers. You could add another five nodes, bringing the total number of nodes to 10, while still using just the three configuration databases to support all 10 nodes.

Installing the configuration database to a separate server has the following advantages:

- More CPU is available to the server for running jobs, process flows, and service requests because reading and writing to the configuration database is handled by a separate server.
- Reduced network traffic due to reduced configuration data replicated between nodes. For example, you could have five Spectrum™ Technology Platform servers for handling execution while having only three repositories. With just three repositories instead of five, data only needs to replicate between three servers rather than five.
- Most scalable installation scenario.



## System Requirements

### Server

#### Operating Systems

Supported Operating System

Notes

---

**Windows Server 2008 R2**

---

**Windows Server 2012**

---

**Windows Server 2012 R2**

---



Supported Operating System	Notes
----------------------------	-------

**Windows Server 2016**

*Unsupported Operating Systems by Module*

The following table shows the operating systems that are not supported for specific modules.

Module	Not Supported
Enterprise Geocoding Module (U.S.)	Windows Server 2016
Enterprise Tax Module	Windows Server 2016
GeoEnrichment Module	Windows Server 2016
Global Geocoding Module	Red Hat Linux 5.x (not supported for U.S.) Windows Server 2016 (not supported for U.S.)
Universal Addressing Module Loqate	AIX 7.2

## Disk Space

### New Installation

- The disk where you are installing Spectrum™ Technology Platform must have 4 GB of free space to install all modules, less if installing fewer modules.
- The disk where the temp folder is located must have at least 10 GB of free space for the installation to extract the files it needs. You may need more depending on the options you are installing. If necessary, modify your TEMP environment variable (Windows) or IATEMPDIR environment variable (Unix and Linux) to point to a location with enough space.

### Upgrade

- The disk where you are installing Spectrum™ Technology Platform must have free disk space equal to three times the size of your current installation. To determine the size of your current installation, look at the size of the folder where you installed Spectrum™ Technology Platform.
- If you are adding modules as part of your upgrade, you will need 3 GB to install all modules, less if installing fewer modules.
- The disk where the temp folder is located must have 10 GB of free space plus four times the size of your current installation. For example, if your current installation is 5 GB, you would need 30 GB of temp space:  $(4 \times 5 \text{ GB}) + 10 \text{ GB} = 30 \text{ GB}$ . If necessary, modify your TEMP environment variable (Windows) or IATEMPDIR environment variable (Unix and Linux) to point to a location with enough space.

**Note:** If you are installing a module that uses a reference database, such as a postal database, geocoding database, or data normalization tables, you will need space for this data. The total disk space varies, depending on which modules and databases you are installing.

## Memory

- Basic memory requirement: 16 GB
- The Enterprise Geocoding Module requires an additional 500 MB memory for the first non-U.S. geocoder, and 250 MB for each additional non-U.S. geocoder, with these exceptions:
  - Germany, Australia, and the U.K. each require 1 GB additional memory
  - Japan requires 2 GB additional memory
- The Data Normalization Module and Universal Name Module require additional memory if you use these name databases:
  - Arabic Plus Pack: 5.5 GB
  - Asian Plus Pack - Chinese: 32 MB
  - Asian Plus Pack - Japanese: 1.6 GB
  - Asian Plus Pack - Korean: 8 MB
  - Core Names: 1.1 GB

## Additional Requirements

- Windows administrator rights are required to install Spectrum™ Technology Platform

- In order to use the enhanced system tray notification application the server must have .NET Framework 3.5 SP1 (also known as 3.5.1) or higher. Windows Server 2008 comes with a limited version of .NET Framework 3.5. You need install the full .NET Framework 3.5.1 on Windows Server 2008. Later versions of Windows Server come with the required version of .NET Framework.

#### Requirements for the Big Data Integration Module

For the stages using Hadoop, which are **Read from Hive File**, **Read from Hadoop Sequence**, **Write to Hadoop Sequence**, and **Write to Hive File**, and for the activities **Run Hadoop MapReduce Job** and **Run Hadoop Pig**:

- Hadoop version 2.6 and above

For the activities using Spark, which are **Submit Spark Job** and **Spark Sorter**:

- Spark 2.0.1 and above.

## Network Ports

The Spectrum™ Technology Platform server uses several network ports for communication. Network port conflicts can result in module components failing to start. One indication that a component has failed to start is if it does not appear in Management Console. To troubleshoot the problem, look in the Spectrum™ Technology Platform wrapper log. This log shows which port is causing the problem. You can find the Spectrum™ Technology Platform wrapper log in:

```
server\app\repository\logs\wrapper.log
```

You can change the ports by modifying the properties in this file and restarting the server:

```
server\app\conf\spectrum-container.properties
```

**Note:** In a clustered environment you must modify the `spectrum-container.properties` file on *each node* in the cluster.

Port	Description
5001	<p>This port is used by the Spectrum™ Technology Platform configuration database.</p> <p>To use a different port in a non-clustered environment, modify this property:</p> <pre>spectrum.repository.server.coordinator.port</pre> <p>To use a different port in a clustered environment:</p> <ul style="list-style-type: none"> <li>• Specify the port you want instead of 5001 in <code>spectrum.repository.server.coordinator.port</code>.</li> <li>• Specify the seed nodes for the configuration database in <code>spectrum.repository.server.cluster.seeds</code>.</li> </ul>

Port	Description
5701	<p>This port is used by Hazelcast for managing distributed processing between Spectrum™ Technology Platform servers in a cluster.</p> <p>To use a different port in a non-clustered environment, modify this property:</p> <pre>spectrum.hazelcast.port</pre> <p>To use a different port in a clustered environment:</p> <ul style="list-style-type: none"> <li>• Specify the port you want to use instead of 5701 in <code>spectrum.hazelcast.port</code>.</li> <li>• Include the Hazelcast port number after each IP address specified in <code>spectrum.cluster.seeds</code>. For example, if <code>spectrum.hazelcast.port</code> is set to 5702 and the IP address of a seed node is 1.2.3.4.5, you would specify <code>1.2.3.4.5:5702</code> in <code>spectrum.cluster.seeds</code>.</li> </ul>
6362	<p>This port is used if you enable backups of the Spectrum™ Technology Platform configuration database. To use a different port, modify this property:</p> <pre>spectrum.backup.http.port</pre>
7474	<p>This port is used by the Spectrum™ Technology Platform configuration database. To use a different port, modify this property:</p> <pre>spectrum.repository.server.connector.http.port</pre>
7687	<p>This port is used by the Spectrum™ Technology Platform configuration database. To use a different port, modify this property:</p> <pre>spectrum.repository.server.connector.bolt.port</pre>
8080	<p>The port used for communication between the server and Enterprise Designer and Management Console. This port is also used by web services. To use a different port, modify this property:</p> <pre>spectrum.http.port</pre>
9200	<p>This port is used by the search index engine used by the Advanced Matching Module. To use a different port, modify this property:</p> <pre>spectrum.index.http.port</pre>

Port	Description
9300	<p>This port is used by the search index engine used by the Advanced Matching Module.</p> <p>To use a different port in a non-clustered environment, modify this property:</p> <pre>spectrum.index.tcp.port</pre> <p>To use a different port in a clustered environment:</p> <ul style="list-style-type: none"> <li>• Specify the port you want to use instead of 9300 in <code>spectrum.index.tcp.port</code> and after the colon in <code>spectrum.index.client.addresses</code>.</li> <li>• Specify the seed nodes for the search index in <code>spectrum.index.server.cluster.seeds</code>.</li> </ul>
10119	<p>This port is used for API calls made to services. To use a different port, modify this property:</p> <pre>spectrum.socketgateway.port</pre>
32750	<p>This port is used for JDBC connections model stores which are created in Metadata Insights. To use a different port, modify this property:</p> <pre>spectrum.metadata.jdbc.port</pre>
32751	<p>This port is used for ODBC connections model stores which are created in Metadata Insights. To use a different port, modify this property:</p> <pre>spectrum.metadata.odbc.port</pre>

## Enterprise Designer

Enterprise Designer requires the following:

- Operating system requirements:
  - Windows 7
  - Windows 10
- 86 MB of disk space to install Enterprise Designer without any modules. Each module you install requires additional disk space.
- Microsoft .NET Framework 4.6 (available from the Spectrum™ Technology Platform Welcome Page, <http://<SpectrumServerName>:8080>)
- A monitor with at least 1024 x 768 resolution
- Maximum Windows DPI setting: 150%
- Adobe Reader 7 or later (for viewing and saving reports)

## Web browsers

- Internet Explorer 11
- Google Chrome 56 or later
- Firefox 51 or later
- To use the Data Hub Relationship Analysis Client, a browser with Microsoft Silverlight 5 installed. See [www.microsoft.com/getsilverlight](http://www.microsoft.com/getsilverlight). Because Google Chrome no longer supports Microsoft Silverlight, you will need to access these client tools using Internet Explorer or Firefox.

## Command line tools

### *Administration utility*

- Operating system requirements:
  - Windows 7
  - Windows 10
- The Administration Utility requires Java 8 or later. Verify that Java 8 is in the system's path before running the Administration Utility.

### *Job executor and process flow executor*

These tools require Java 8 or later.

## User Interface Languages

Spectrum™ Technology Platform user interfaces such as Management Console, Enterprise Designer, and web applications are localized for these languages:

- English
- French
- German
- Japanese
- Spanish

## Client SDK

The Client SDK provides API access to Spectrum™ Technology Platform services. To use the Client SDK your computer must meet these requirements:

- 1.25 GB disk space
- JDK 1.5 is required to install the Client SDK. Be sure that JDK 1.5 is in the PATH environment variable. Once installed, the Client SDK supports JDK 1.4 and greater.

### Supported compilers

The Spectrum™ Technology Platform Client SDK is supported with the compiler and runtime minimum versions listed here.

#### Java

Client SDK Package Directory: `clientsdk/platforms/java`

Client SDK requires the Java JDK, version 1.4 or higher. This is not installed with the Client SDK.

#### Windows 32-bit

- JDK: 1.4
- C Compiler: MSVC 6.0 SP3, MSVC 2003, MSVC 2005, MSVC 2008
- C++ Compiler: MSVC 6.0 SP3, MSVC 2003, MSVC 2005, MSVC 2008
- C# .NET: Microsoft .NET Framework 1.1
- Visual Basic: MS Visual Basic 6.0

#### Windows 64-bit

- JDK: 1.4
- C Compiler: MSVC 2005, MSVC 2008
- C++ Compiler: MSVC 2005, MSVC 2008

#### HP-UX RISC

- JDK: 1.4
- C Compiler: cc: HP92453-01 A.11.01.21 HP C (Bundled) Compiler
- C++ Compiler: aCC: HP aC++ B3910B A.03.30 HP aC++ B3910B A.03.27

The `clientsdk` 32-bit lib is linked to these libraries:

- `libpthread.1`
- `librt.2`
- `libnsl.1`
- `libxti.2`

The clientSDK 64-bit lib is linked to these libraries:

- libpthread.1
- libnsl.1
- librt.2
- libdl.1
- libc.2
- libxti.2
- libdl.1

#### *HP-UX Itanium*

- JDK: 1.4
- C Compiler: cc: HP aC++/ANSI C B3910B A.06.05
- C++ Compiler: aCC: HP aC++/ANSI C B3910B A.06.05

The clientSDK 32-bit lib is linked to these libraries:

- libpthread.so.1
- libnsl.so.1
- librt.so.1
- libxti.so.1
- libdl.so.1

The clientSDK 64-bit lib is linked to these libraries:

- libpthread.so.1
- libnsl.so.1
- librt.so.1
- libxti.so.1
- libdl.so.1

#### *Red Hat (32-bit)*

- Operating System: Red Hat Linux 2.4.9-e.65smp
- C Compiler: gcc version 2.96 (gcc 4.1 required for the Address Now Module)
- C++ Compiler: g++ version 2.96

The clientSDK lib is linked to these libraries:

- libstdc++-libc6.2-2.so.3
- libm.so.6
- libc.so.6
- ld-linux.so.2

#### *Red Hat (64-bit)*

- Operating System: Red Hat Linux version 2.6.9-34.0.2.ELsmp



- C Compiler: gcc version 3.4.5
- C++ Compiler: g++ version 3.4.5

The clientSDK lib is linked to these libraries:

- libstdc++.so.6
- libm.so.6
- libgcc\_s.so.1
- libpthread.so.0
- libc.so.6
- ld-linux-x86-64.so.2

### *SuSE*

- Operating System: SuSE SLES 8 (powered by UnitedLinux 1.0) (i586)\nKernel 2.4.21-295-smp (0).
- C Compiler: gcc version 3.2.2
- C++ Compiler: g++ version 3.2.2

The clientSDK lib (32-bit) is linked to these libraries:

- libstdc++.so.5
- libm.so.6
- libgcc\_s.so.1
- libc.so.6
- ld-linux.so.2

### *Solaris*

- Operating System: Solaris 5.8
- C Compiler: cc: Forte Developer 7 C 5.4 2002/03/09
- C++ Compiler: CC: Forte Developer 7 C++ 5.4 Patch 111715-16 2005/04/28

The clientSDK 32-bit lib is linked to these libraries:

- libpthread.so.1
- libsocket.so.1
- libnsl.so.1
- librt.so.1
- libc.so.1
- libdl.so.1
- libmp.so.2
- libaio.so.1
- libc\_psr.so.1

The clientSDK 64-bit lib is linked to these libraries:

- libpthread.so.1

- libsocket.so.1
- libnsl.so.1
- librt.so.1
- libc.so.1
- libmp.so.2
- libmd5.so.1
- libscf.so.1
- libaio.so.1
- libdoor.so.1
- libuutil.so.1
- libm.so.2
- libc\_psr.so.1
- libmd5\_psr.so.1

### AIX

- Operating System: AIX version 5.1.0.0
- C Compiler: xlc 6.0 Visual Age C 6.0
- C++ Compiler: xlc 6.0 Visual Age C++ 6.0

The clientSDK 32-bit and 64-bit lib are linked to these libraries:

- libC.a
- libc\_r.a
- libpthread.a
- librtl.a

## Location Intelligence Module support

### Database

The Location Intelligence Module supports the following spatial databases for use with the spatial services, data, and resources:

- Oracle 11gR2, Oracle 12C
- SQL Server 2012, 2014, and 2016
- SAP HANA 9.3
- PostgreSQL 8+ (PostGIS 2.x)

**Note:** Spectrum Spatial requires the PostGIS extension for PostgreSQL data source provider even if spatial capability will be not needed or used.

- GeoPackage (Windows and CentOS)

### Data format

The Location Intelligence Module supports the following data formats for use with the spatial services:

- Generic JDBC (with XY)
- TAB (native, native extended, raster, grid, seamless, DBF)
- ESRI shapefile

### Raster format

The following raster and grid formats (64-bit only) are supported in the Location Intelligence Module:

#### Raster formats:

Format	File Extension
ADRG	.gen
ASRP	.gen
BMP	.bmp, .wbmp
CADRG	.gen
CIB	various
ECW (SDK v5)	.ecw
GeoTiff	.geotif
GIF	.gif
JPEG	.jpg/.jpeg
MrSID (SDK v9)	.sid
<p><b>Note:</b> Supports MG4 (MrSID Generation 4). On CentOS 7.1, libpng12.so is required for reading MrSID rasters.</p>	
NITF	.ntf
PNG	.png
TIFF	.tif
<p><b>Note:</b> TIFF files used by the Feature Service and Mapping Service cannot exceed 2GB.</p>	

**Note:** Solaris or AIX machines, whether installed with 32- or 64- bit JVM, do not support ECW and MrSID raster formats.

#### Grid Formats

Format	File Extension
Defense Digital Terrain Elevation Data (DTED)	.dt0, .dt1, .dt2, .dt3
MapInfo Grid	.mig

MRR (Multi-Resolution Raster)	.mrr
<p><b>Note:</b> This support is provided on Windows and the following Linux environments:</p> <ul style="list-style-type: none"> <li>• Oracle Linux 6.5 and 7.1</li> <li>• CentOS 6.4 and 7.1</li> <li>• Ubuntu 12.04, 14.04, and 16.04</li> </ul>	
Vertical Mapper Classified Grid	.grc
Vertical Mapper Continuous Grid	.grd

In order to use rasters and grids as a map layer, there must be an associated .TAB file containing georeference information about the image, including the bounds, coordinate system, and registration points.

### Utilities

The Location Intelligence Module utilities (Tile Generator, WMTS Tile Generator, and the Geometry Validator) require at a minimum Java 8. If you are installing these utilities on the same computer where the Spectrum™ Technology Platform server is installed, Java 8 will be installed since it is included with the server. If you want to install the utilities on another computer, make sure that the computer has Java 8 or later installed.

### Samples

The .NET samples require at a minimum Visual Studio 2013 and Microsoft .NET Framework 4.5.

### MapInfo Professional compatibility

The Location Intelligence Module is compatible with MapInfo Professional up to version 16.x. See Tools > MapInfo Pro in the *Spectrum Spatial Getting Started Guide* for more information about the interoperability of the two products.

### Internet Explorer

To use Internet Explorer 11, uncheck **Display intranet sites in Compatibility View** in the Compatibility View settings.

### WebDAV

When communicating to the server over HTTPS to map a drive to the repository, a WebDAV client is required to use the TLS v1.2 protocol. For client machines running on Windows 7 SP1, Windows Server 2008 R2 SP1, and Windows Server 2012, you must apply a security patch and registry update to leverage this protocol. For instructions, see the "Managing Security" chapter in the Administration section of the *Spectrum Spatial Guide*.

# 2 - Standard Installation

## In this section

---

Installing a New Server	22
Upgrading a Server	23
Installing a License Key	27
Installing the Server with a Silent Installer	28
Adding Modules	28
Removing the Server	29

## Installing a New Server

### Prerequisites:

- Before installing Spectrum™ Technology Platform, be sure to read the release notes. The release notes contains important compatibility information as well as release-specific installation notes.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.
- You may encounter installation problems on Windows if the data execution prevention (DEP) setting is not set correctly. The DEP setting must be set to **Turn on DEP for essential Windows programs and services only**. For instructions on how to change your DEP setting, see the Windows documentation.

### To install a new server:

1. Download Spectrum™ Technology Platform using the download instructions contained in your welcome letter.
2. Extract the downloaded file to a temporary location on the server where you want to install Spectrum™ Technology Platform.
3. Double-click `install.exe`.
4. The installer guides you through the installation process. Note the following:
  - If you are setting up an environment where the configuration database is installed on a separate server choose **Server only**. Otherwise choose **Standard installation**.
  - When prompted, select the modules that you want to install.
    - Make sure that Spectrum™ Technology Platform is selected.
    - If you are installing the SAP Module you must install these modules: **Address Now Module** and **Advanced Matching Module**. The Enterprise Tax Module is optional. The **Universal Addressing Module** is only required if you will be using the SAP module service `SAPValidateAddressWithCandidates`.
    - If you are installing the Siebel Module you must install these modules: **Advanced Matching Module**, **Data Normalization Module**, and **Universal Name Module**. You may need to install one or more of these modules depending on the features you have licensed: **Address Now Module**, **Enterprise Geocoding Module**, and **Universal Addressing Module**.
  - When prompted, enter the HTTP port that you want to use then press **Enter**. The default is 8080. For a complete listing of ports used by Spectrum™ Technology Platform see [Network Ports](#) on page 11.
5. Unless you are installing a cluster and you cleared the check box to start the server after installation, the Spectrum™ Technology Platform server starts when the installation is complete. Wait for the server to start.

You can see when the server has fully started by opening the log file <Spectrum Installation Location>\server\app\repository\logs\wrapper.log and looking for this message:

```
INFO [Server] Pitney Bowes Spectrum(TM) Technology Platform (Version
version build) Started
```

**Important:** Do not attempt to stop the server until after it has fully started for the first time. Stopping the server before it performs an initial startup can cause your installation to become unusable.

6. Install your license key. For more information, see [Installing a License Key](#) on page 27.
7. Apply all the updates for the platform and any modules you have installed. For a listing of updates, see the [Update Summary](#) on the Pitney Bowes support website.

## Upgrading a Server

Prerequisites:

- Before upgrading, be sure to read the release notes for the new version. The release notes contain important compatibility information, supported upgrade paths, and module-specific data backup recommendations.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.

This procedure is for upgrading a single Spectrum™ Technology Platform server. Follow this procedure when upgrading a standard installation or when upgrading a node in a cluster. If you are upgrading a cluster, be sure to follow the cluster upgrade process. For more information, see [Upgrading a Cluster](#) on page 47.

If you use remote servers, you must upgrade the remote servers and start them before upgrading the main server. If you upgrade the main server and start it before upgrading and starting the remote servers, you will need to recreate the remote server connections in Management console after upgrading.

1. Download the updated version of Spectrum™ Technology Platform using the download instructions contained in the release announcement email.
2. Unzip the downloaded installer to a temporary folder on the server you want to upgrade.
3. Back up the server. For instructions on creating a backup, see the *Administration Guide*.

**Important:** We recommend that you create a backup before upgrading so that you can recover your flows, security settings, and other settings, if an error occurs during the upgrade process.

4. Back up module-specific data for any of these modules if you have them installed.

Module	Items to Back Up
Advanced Matching Module, Data Normalization Module, and Universal Name Module	<p>Back up the contents of these subfolders located in <i>SpectrumLocation/server/modules</i>:</p> <ul style="list-style-type: none"> <li>• cdqdb</li> <li>• lucene</li> <li>• matcher</li> <li>• parser</li> <li>• searchindex</li> <li>• tables</li> </ul>
Data Hub Module	<p>Open the Relationship Analysis Client and click <b>Manage</b>. Select the model you want to back up then click <b>Backup</b>.</p> <p>In addition to backing up your models, back up these two property files:</p> <ul style="list-style-type: none"> <li>• server\modules\hub\hub.properties</li> <li>• server\modules\db\neo4j.properties</li> </ul>
Location Intelligence Module	<p>Back up your named resources, data, and configuration files.</p>

- (Optional) You can reduce the time it takes to upgrade your system by purging old records from the execution history. Consider purging the execution history if it contains over 100,000 entries. You can view your execution history in Enterprise Designer under **View > Execution History**.

If you are upgrading from 9.0 SP3 or 10.0 SP1, delete old history records manually using Management Console.

If you are upgrading from version 11.0, 11.0 SP1, or 12.0, use the JMX console to delete old history records. This process is faster than manually deleting records in Management Console, but is only available on versions 11.0, 11.0 SP1, and 12.0. For more information, see [Purging Execution History](#) on page 25.

- Stop the Spectrum™ Technology Platform server. To stop the server, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Stop Spectrum™**. Alternatively, you can use the Windows Services control panel and stop the Pitney Bowes Spectrum™ Technology Platform service.
- Wait for the server to finish the shutdown process before proceeding.

**Important:** If you have the Data Hub Module installed, make sure that all models shut down properly. Models that do not shut down properly will not open successfully after upgrading.



8. If you have the Address Now Module installed, stop the Address Now server by going to the Windows services control panel and stopping the Address Now Server service.
9. If you have the Global Sentry Module installed, stop the Global Sentry database server by going to the Windows services control panel and stopping the Global Sentry Database Server service.
10. Run the Spectrum™ Technology Platform installer to upgrade your system.
11. Apply all the updates for the platform and any modules you have installed. For a listing of updates, see the [Update Summary](#) on the Pitney Bowes support website.

**Note:** Any job or subflow stored in the system during a server upgrade is marked as exposed to provide the same behavior for those jobs and subflows as before the upgrade. Any job or subflow that is exported prior to the upgrade will not be exposed. Therefore, when importing these jobs or subflows back into the system, you must manually expose the imported job or subflow.

Some modules have post-upgrade steps you need to perform.

#### Data Hub Module

Open this file in a text editor:

`server/modules/hub/neo4j.properties`  
and set the property `allow_store_upgrade` property to true. The purpose of this property is to protect against unintentional and irreversible store upgrades. Setting this property to "true" indicates that you understand the ramifications of proceeding with an upgrade and have taken the necessary precautions before proceeding.

Restart the Spectrum™ Technology Platform server. The server will upgrade each model. Examine the file `server/app/repository/logs/wrapper.log` for errors or warning messages. Once all models have been upgraded, go back to the `hub.properties` file and comment out the `allow_store_upgrade` property.

---

## Purging Execution History

If you have many flows, or services that are used frequently, the execution history in Management Console can become quite large. This procedure describes how to remove old records from the execution history. You may want to purge old records to reduce the size of the configuration database. Purging records before upgrading to a new version can help reduce the time it takes to upgrade Spectrum™ Technology Platform.

1. Open a web browser and go to `http://server:port/jmx-console`

Where:

`server` is the IP address or hostname of your Spectrum™ Technology Platform server.

*port* is the HTTP port used by Spectrum™ Technology Platform. The default is 8080.

2. Under **Domain: com.pb.spectrum.platform.config**, click **com.pb.spectrum.platform.config:manager=ArchiveTransactionManager**.
3. (Optional) If you want to save an archive of the history that you are going to purge, specify the path where you want to save the archive in the **ArchiveDirectory** field, then click **set**. Then, set **ArchiveEnabled** to **true** and click **set**.
4. In the **ArchiveRetain** field, specify how many days of records you want to keep in the history then click **set**. For example, if you enter 45 then history records that are 45 days old or newer will be retained, and records 46 days old and older will be purged. To determine how many days of records you can retain, look at the job and process flow history in Enterprise Designer and identify the point in time where the number of records exceeds 100,000.
5. (Optional) If you want to schedule a purge to occur on a regular schedule, enter the schedule in the **CronExpression** field using a Cron expression.

A cron expression consists of six space-separated values, with an optional seventh value:

Seconds  
 Minutes  
 Hours  
 Day of the month  
 Month  
 Day of the week  
 Year (Optional)

For example, this expression would purge the flow and transaction history at midnight every Sunday:

```
0 0 0 ? * SUN
```

For more information about cron expressions, see [quartz-scheduler.org/documentation](http://quartz-scheduler.org/documentation).

After specifying a cron expression, click the **set** button next to the **CronExpression** field, set **PurgeEnabled** to **true**, and click the **set** button next to the **PurgeEnabled** field.

**Note:** You do not need to schedule purges if you want to purge the history only one time for the purposes of speeding up the upgrade process.

6. (Optional) If you want to set a maximum number of records to remain in the history after the purge, specify the maximum number of records in the **MaxHistoryRecordCount** field. This is useful if you have a large number of history records each day, and even after purging old records based on the value in the **ArchiveRetain** field, the size of the execution history is still larger than you want. After purging the old records based on the value in the **ArchiveRetain** field, additional records will be purged until the number of records that remains is equal to the number in the **MaxHistoryRecordCount** field. If you do not want to specify a maximum number of history records, specify **-1**.

**Note:** The limit you specify in **MaxHistoryRecordCount** sets the limits for process flows and jobs separately. For example, if you specify 5000, the maximum number of process flow history records will be 5,000, and the maximum number of job history records will be 5,000, for a total maximum number of 10,000 records.

7. In the **PurgeOperation** field, leave the value set to `ALL`.
8. To run the purge, click **Invoke**.

You have purged flow and execution history so that you now have a smaller configuration database.

## Installing a License Key

The license key provides access to software pursuant to the terms of your license. It is an encrypted XML file with a file name ending in `.key`.

**Note:** When you upgrade an existing Spectrum™ Technology Platform installation, you may continue to use your existing license key. You do not need to get a new one.

To install a license key:

1. Locate the email containing your license key that you received from Pitney Bowes.

**Important:** You must install the license key within 45 days of receiving it. If you do not you will need to contact Pitney Bowes for another license key.

2. Copy the `.key` file to the following directory:

```
<SpectrumPlatformLocation>\server\app\import
```

The license key is applied to your system. There is no need to restart your server.

If there was a problem installing the license key, check the log file in:

```
<SpectrumPlatformLocation>\server\app\repository\logs
```

Depending on whether the key was processed successfully or there was an error processing the key, the processed key goes into one of these folders:

- `<SpectrumPlatformLocation>\server\app\import\archive\license-keys`
- `<SpectrumPlatformLocation>\server\app\import\error\license-keys`

## Installing the Server with a Silent Installer

The silent install process for the server allows you to pre-configure the server installation process so that it runs without user intervention. Instead of responding to prompts for information such as the installation location and which modules to install, you specify these responses in a properties file which the installer uses instead of user prompts.

1. In the Spectrum™ Technology Platform installer, go to the folder `SilentInstaller`.
2. Open the file `installer.properties` in a text editor.
3. Edit `installer.properties` as necessary to specify the installation settings you want to use. See the comments in `installer.properties` for additional information.
4. To run the installer in silent mode, place `installer.properties` in the same directory as `install.exe`. When the installer executes it will detect `installer.properties` and automatically run in silent mode.

Alternatively, you can place `installer.properties` in different directory and give the absolute path to the property in the command prompt using the `-f` argument, as follows:


```
install.exe -f PathOfPropertyFile\installer.properties
```

## Adding Modules

Spectrum™ Technology Platform is designed so that modules can be added as you grow your system over time. For example, you may have one Spectrum™ Technology Platform module and then license another module a few months later. The second product may be built on a newer version of Spectrum™ Technology Platform. This will require you to upgrade your version of Spectrum™ Technology Platform. In another case, the second product is compatible with the installed version. In both cases, the install program recognizes if it needs to upgrade Spectrum™ Technology Platform and will do so without prompting. If an upgrade is not required, the installer will skip the Spectrum™ Technology Platform install steps and install the new module.

The process for adding a module is similar to that of a new installation. In both cases you start the installation process by running the Spectrum™ Technology Platform installer. Note that Spectrum™ Technology Platform modules do not have their own installer. Instead, you use the Spectrum™ Technology Platform installer to add modules.

1. If the Spectrum™ Technology Platform server is running, stop it. To stop the server, right-click the Spectrum™ Technology Platform icon in the Windows system tray (shown below) and select **Stop Spectrum™**.




2. Launch the Spectrum™ Technology Platform installer by double-clicking `Install.exe`. The installer guides you through the installation process. When prompted, select the modules that you want to install. Your currently installed modules are selected.
3. Install any necessary databases for the new product. For more information on installing databases, see [Spectrum Databases](#) on page 75.
4. After you install the necessary databases (if any), start Spectrum™ Technology Platform by right-clicking the Spectrum™ Technology Platform icon in the Windows system tray and selecting **Start Spectrum™**.
5. Install the license key for the module. For instructions, see [Installing a License Key](#) on page 27.

## Removing the Server

Before uninstalling any product, back up any files you may need in the future. Uninstalling Spectrum™ Technology Platform will remove all jobs and settings.

1. If the Spectrum™ Technology Platform server is running, stop it. To stop the server, right-click the Spectrum™ Technology Platform icon in the Windows system tray (shown below) and select **Stop Spectrum™**.



2. Go to **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Server** and select **Uninstall Pitney Bowes Spectrum™ Technology Platform**.

**Note:** Some Java files will not be removed because the uninstall process itself uses them.

# 3 - Cluster

## In this section


---

Clustered Architecture	32
Requirements	36
Installing a Cluster	36
Installing a Cluster for the Location Intelligence Module	42
Upgrading a Cluster	47
Upgrading a Cluster with the Data Hub Module	48
Upgrading a Cluster with the Location Intelligence Module	51
Removing a Node from a Cluster	53
Adding Modules to a Cluster	54
Starting a Cluster	55
Stopping a Cluster	56
Using Enterprise Designer with a Cluster	56

## Clustered Architecture

In a clustered environment, processing is shared among two or more instances of the server. All communication with Spectrum™ Technology Platform goes through a load balancer. Instead of using the URL and port of the Spectrum™ Technology Platform server, you use the URL and port of the load balancer. Consider using this approach if you require failover redundancy and high-volume, high-performance processing.

This diagram illustrates the cluster architecture:



### Load Balancer

As requests come into the cluster, the load balancer identifies the best available Spectrum™ Technology Platform node to handle the request. The request is then passed to a Spectrum™ Technology Platform node.

From the user's perspective, the distributed architecture is handled automatically behind the scenes. The user sends a request to the load balancer's URL and port for Spectrum™ Technology Platform (typically port 80 for a distributed environment) as if it were a single Spectrum™ Technology Platform server.

### Nodes

A node is a Spectrum™ Technology Platform server installation. Each node has a copy of the configuration database. Each copy is continuously synchronized. This enables each node to share the same settings, such as license information, dataflows, and database resources.

To configure the cluster, simply point Management Console or Enterprise Designer to the load balancer's URL and port for Spectrum™ Technology Platform (typically port 80 for a distributed environment).



### External Resources

The definitions for external resources such as database resources (postal databases and geocoding databases for example), JDBC connections, and file servers, reside in the configuration database. The resources themselves (databases, files, web services) can reside anywhere you choose. Database resources can be installed either on each node in the cluster or on a shared network location.

Because the database resources themselves reside outside the cluster, multiple clusters can share the same database resources. You must create the resource definitions in each cluster using Management Console. For example if you want multiple clusters to share the same geocoding database, you can install the geocoding database on a server accessible from each cluster, then in Management Console point each cluster to the geocoding database.

### Installing a Cluster

For instructions on installing a cluster, see the *Spectrum™ Technology Platform Installation Guide*.

## Clustered Architecture for the Data Hub Module


In a clustered environment, Data Hub Module graph databases are replicated to each Spectrum™ Technology Platform server in the cluster. The server that receives the first request to open a model is the master. All other servers maintain a replicated mirror of that master. If different servers receive requests to open different models, the masters for the models are on different servers. All writes to the database are synchronized with the master. Any server can process read requests.

We recommend that clusters have a minimum of three servers in order to achieve a level of fault tolerance. Also, an odd number of servers provide better resiliency per server than an even-numbered cluster. We make these recommendations because once the model is running, the system will continue running as long more than half the servers are in communication. For example, in a cluster of six servers, four must stay in communication; for a cluster of three servers, two must stay in communication, and for a cluster of two servers, all servers must be in communication. Both a three-server cluster and a four-server cluster can tolerate a maximum of one lost server.

All servers in the cluster must be available in order to open or create a model. If any server is unavailable, the server will wait for all servers to join the cluster. If this number of servers do not join within the timeout period, the operation fails.

## Clustered Architecture for the Global Geocoding Module

In a clustered environment, processing is shared among two or more instances of the server. The diagram below illustrates the deployment architecture of such a configuration. Load balancing can be used to support high availability and scaling. The deployment architecture includes a load balancer, Spectrum™ Technology Platform nodes with Global Geocoding Modules and Geocoding databases.




**Note:** Each Geocoding database MUST be installed in the same location on all of the nodes for the cluster to work properly. For example, if the Geocoding database for “Spectrum Node 1” is installed on `C:\data\`, then the other Spectrum nodes' Geocoding database must also reside on `C:\data\`.

## Clustered Architecture for the Location Intelligence Module

In a clustered environment, processing is shared among two or more instances of the server. The diagram below illustrates the deployment architecture of such a configuration. Load balancing can be used to support high availability and scaling. The deployment architecture includes a load balancer, a Spectrum Spatial cluster, a database, and a file share. With this approach it is possible to scale both horizontally and vertically. You can cluster the Location Intelligence Module with or without platform clustering.

**Note:** Setting up both a Spectrum™ Technology Platform cluster and a Location Intelligence Module cluster is recommended and has several benefits:

- Security (ACL) synchronization happens automatically for named resources .
- Dataflows, users, and roles created on one node will automatically synchronize to all nodes.
- All Location Intelligence Module demo pages and utilities (such as Spatial Manager) can and should point to the load balancer.



### *Load Balancer*

The load balancer spreads requests between the Spectrum Spatial instances. Any load balancer that supports load balancing HTTP/HTTPS requests can be used.

### *Spectrum Spatial Cluster*

The cluster is a collection of Spectrum instances with LIM sharing administration, named resources, geographical metadata content and configuration settings. Additional nodes can be added to the cluster for resilience or to deliver support for greater loads. Each node can be scaled vertically through additional hardware resources and/or additional instances should this be required for hardware with massive resources. Spectrum can be configured to use restricted numbers of CPUs.

### *Database*

Spectrum stores named resources (maps, layers, tables and styles), geographic metadata and configuration in a repository. In the default single server installation an embedded database is used to store these resources on the local server. To create a resilient scalable solution this embedded database should be replaced with a resilient independent database. Oracle, PostgreSQL/PostGIS and Microsoft SQL Server are the supported repository databases.

In the load balanced configuration, Spectrum nodes cache these resources in a local cache and search index in each node in the cluster. When a Spectrum node receives a request it uses the local cache and index to find resources. Named resources can be added through any node in the cluster. Each node keeps its cache current by checking for differences between its local cache and the central database. This check occurs every 2 seconds by default. Time frequency can be configured. This architecture ensures the server delivers high performance transactions and the load on the repository database is kept to a minimum. If a new Spectrum node is added to the cluster the cache and index are created automatically. Such a scenario can occur to remedy a node failure or grow the capability of the deployment.

### *File Share*

The file share provides a folder to hold map images generated by Spectrum. When maps are rendered using the web services the server supports the map images being returned through URLs or returned as a base 64 encoded image. When a URL is returned the map image is stored as a file and served on request of the URL. To ensure any Spectrum node can return the map image a file share is used to store the images.


## Requirements

- A cluster should consist of at least three nodes.
- All servers that host a node must have their system clocks synchronized in order for the cluster to function. Verify that all systems point to the same time service to synchronize their clocks.
- All nodes in a cluster must be the same version of Spectrum™ Technology Platform so be sure that the version you install is the same as the existing nodes.
- All nodes in a cluster must have the same modules installed.


## Installing a Cluster

Installing a cluster involves setting up one Spectrum™ Technology Platform server at a time. Each time you add a server you need to point it to an existing server which will act as a seed node. A *seed node* is a server that has a copy of the Spectrum configuration data that it can copy to a new node so that the new node's configuration is synchronized with the other nodes in the cluster. The following diagrams illustrate this process.


After installing the first node you will in effect have a cluster with only one node:



When you install the second node it must point to the first node as a seed node. This will enable the second node to receive a copy of the first node's configuration database, resulting in a cluster with two nodes with synchronized configuration information.



As you add additional nodes, the new nodes can point to any of the existing nodes as a seed node. You must also configure the first node to point to at least one other node in the cluster so that if it is ever brought down it can rejoin the cluster.



Before you begin, install a load balancer. You can choose for yourself an appropriate load balancer. Follow the procedures described in the load balancer's documentation when installing.

**Note:** The load balancer must be configured to allow encoded forward slashes. If the load balancer does not allow encoded forward slashes you may get HTTP 404 errors while using the cluster. For example, if you are using an Apache load balancer, you can configure it to allow encoded forward slashes by opening the `httpd.conf` file and specifying this property: `AllowEncodedSlashes On`. For other types of load balancers, refer to the load balancer's documentation.

Once you have your load balancer installed, follow these steps to install nodes in the cluster.

1. Install Spectrum™ Technology Platform on a server where you want to host a node. For instructions, see [Installing a New Server](#) on page 22.

**Important:** The installer will prompt you to start Spectrum™ Technology Platform after the installation completes. You must disable this option so that the server does not start automatically when the installation completes.

2. Configure the properties files.
  - a) Edit the properties in the file `server/app/conf/spectrum-container.properties` as described in [Cluster Properties](#) on page 41.
  - b) Save and close the `spectrum-container.properties` file.
  - c) Some modules have module-specific settings that you must configure to enable the module to work in a cluster.

Module	Cluster Configuration Settings
Advanced Matching Module	<p data-bbox="745 329 1427 415">These settings configure clustering for full-text search indexes. If you do not use full-text search indexes you do not need to configure these settings.</p> <p data-bbox="745 434 1049 459">Open this file in a text editor:</p> <pre data-bbox="745 478 1427 504">SpectrumFolder\server\modules\searchindex\es-container.properties</pre> <p data-bbox="745 527 1032 552">Configure these properties:</p> <p data-bbox="745 575 1260 600"><b>es.index.default_number_of_replicas</b></p> <p data-bbox="927 619 1365 867">Enter the number of additional copies you want created for each search index. This number should be the number of nodes in your cluster minus 1. For example, if your cluster has five nodes, you would enter "4" in this property.</p> <p data-bbox="745 890 1243 915"><b>es.index.default_number_of_shards</b></p> <p data-bbox="927 934 1365 1106">Enter the number of shards you want your index to have in the distributed environment. The more nodes that are in your cluster, the higher this number should be.</p> <p data-bbox="745 1129 1427 1190">Save and close <code>es-container.properties</code> when you are done editing these properties.</p> <p data-bbox="829 1209 1409 1388"><b>Note:</b> Search indexes created prior Spectrum™ Technology Platform 10.0 do not support clustering. To enable clustering for indexes created prior to the 10.0 release, you must recreate the search index using the 10.0 API after modifying the <code>es-container.properties</code> file.</p>

Module	Cluster Configuration Settings
Data Hub Module	<p>Open this file in a text editor:</p> <pre><i>SpectrumFolder</i>\server\modules\hub\hub.properties</pre> <p>Configure these properties:</p> <p><b>hub.models.path.base</b></p> <p>Specifies the folder where models are stored. By default, each model is placed in a subdirectory under the <i>SpectrumFolder</i>\server\modules\hub\db folder. If you want to store models in a different location, uncomment this property and specify the folder where you want to store models.</p> <p><b>hub.neo4j.database.type</b></p> <p>Change the value of this property to ha. The default value embedded is for non-clustered installations.</p> <p><b>hub.servers.per.cluster</b></p> <p>Uncomment this line. Set the value of this property to the number of Spectrum™ Technology Platform servers in the cluster.</p> <p>Save and close <i>hub.properties</i> when you are done editing these properties.</p> <p>The <i>SpectrumFolder</i>\server\modules\hub\db\neo4j.properties controls how the graph databases are configured, using Neo4j Enterprise. This file is used as a template for each model. If needed, each model can be configured separately by placing a copy of this property file into the store directory for that model.</p>

3. Start the server. To start the server, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.
4. Repeat this procedure to install additional nodes in the cluster.
5. After installing all the nodes, go back to the first node and add the other nodes as seed nodes.
  - a) On the first node you installed, open the properties file *server/app/conf/spectrum-container.properties*.
  - b) In the property *spectrum.cluster.seeds*, add the host name or IP address of the other nodes in the cluster, separating each with a comma.



- c) Save and close the `spectrum-container.properties` file. You do not need to restart the server.

## Cluster Properties

The `spectrum-container.properties` file contains the properties that configure a cluster. This table describes how to set the cluster properties for a cluster where the server and configuration database are installed together on each node, and for nodes in the server cluster in a separated configuration database installation. If you are setting up a configuration database cluster, see [Cluster Properties for a Configuration Database Cluster](#) on page 62.

Property	Description
<code>spectrum.cluster.enabled</code>	Set this to true.
<code>spectrum.cluster.name</code>	<p>If this is the first node in the cluster, set this to the name you want to give to the cluster.</p> <p>If this is not the first node in the cluster, set this to the name of the cluster that you want this node to join. If you are unsure of the cluster name, check the <code>spectrum.cluster.name</code> property on another node in the cluster.</p>
<code>spectrum.cluster.address</code>	Specify the node's own IP address.
<code>spectrum.cluster.seeds</code>	<p>If you are setting up the first node in the cluster, or if this is the first node you are starting after having stopped the cluster, specify only the host name or IP address of this server. This effectively points this node to itself as a seed node, which is necessary in order for it to be able to start as the first node in the cluster. Do not specify 127.0.0.1.</p> <p>If this is not the first node in the cluster, specify the host name or IP address of each of the other nodes in the cluster, including nodes that you have not yet installed. Separate each seed node with a comma. When starting up, the node will attempt to access each seed node in the order listed. If none of the seed nodes can be reached, the node will not join the cluster.</p> <p><b>Tip:</b> We recommend that you specify multiple seed nodes so that if one seed node is down others can be used to allow nodes to join the cluster. We also recommend that you specify the same seed nodes in the same order on all nodes in the cluster.</p>

Property	Description
<code>spectrum.cluster.nodeID</code>	<p>Set this to an integer value to use as the ID for this node. The ID must be an integer and must be unique among all nodes in the cluster.</p> <p><b>Tip:</b> We recommend that the first node you install have a node ID of 1, the second one 2, and so on.</p>
<code>spectrum.runtime.hostname</code>	Un-comment this property and set this property to the load balancer host name.
<code>spectrum.runtime.port</code>	Un-comment this property and set this property to the port on which you have configured the load balancer to listen.
<code>spectrum.repository.addresses</code>	<p>Set this to the same IP address specified in <code>spectrum.cluster.address</code>. The default value <code>localhost</code> cannot be used in a clustered environment.</p> <p>If you are configuring a server node in a server-only cluster, specify the IP addresses of the nodes in the configuration database cluster. Separate each with a comma.</p>

## Installing a Cluster for the Location Intelligence Module

To set up a cluster for the Location Intelligence Module, you must first configure a common repository (depending on the type of database you have) then configure your system to prepare it for clustering.

**Note:** Setting up both a Spectrum™ Technology Platform cluster and a Location Intelligence Module cluster is recommended and has several benefits:

- Security (ACL) synchronization happens automatically for named resources .
- Dataflows, users, and roles created on one node will automatically synchronize to all nodes.
- All Location Intelligence Module demo pages and utilities (such as Spatial Manager) can and should point to the load balancer.

### Setting Up a Common Repository Database

You must configure the Location Intelligence Module to use a common repository database for the cluster. This ensures that named resources, geographic metadata and configuration settings are managed across the cluster.

The repository is installed with a set of named resources, geographic metadata and configuration files. To migrate these resources to the common database repository the resources need to be exported from the default internal repository database and reimported into the new shared repository database.

For bulk export and import of repository content, use the `limrepo import` and `limrepo export` commands in the Administration Utility. These commands give you the option of preserving permissions (see the Administration section of the *Spectrum Spatial Guide* for instructions.)

These steps describe how to set up your repository on a common database, either PostgreSQL, Oracle, or Microsoft SQL Server:

1. Export all repository resources to a local folder using the `limrepo export` command in the Administration Utility (see the Administration section of the *Spectrum Spatial Guide* for instructions).

The contents of the installed repository must be exported. This step only needs to be performed once, as the contents of the repository should be the same at this point for all instances of Spectrum™ Technology Platform.

2. Stop the Spectrum™ Technology Platform server on all nodes (for instructions, see [Stopping a Cluster](#) on page 56.)
3. On all nodes of Spectrum™ Technology Platform modify the configuration to specify the common database.
  - a) Copy the contents of `repository.<databaseType>.xml` to `repository.xml` located under the `server/modules/spatial/jackrabbit` folder where `<databaseType>` is the appropriate type for your database (`postgres`, `oracle`, or `mssql`).
  - b) In `repository.xml`:
    - Modify the DataSource section with the server host name, port, database, user, and password.
    - Modify the Cluster section to assign a distinct cluster ID, like Node1. Ensure unique IDs are assigned to every subsequent node in the cluster (for example, Node2, Node3).
    - Save the changes to `repository.xml`.
  - c) Remove these folders from the `/server/modules/spatial/jackrabbit` folder: `repository`, `version`, `workspaces`.
4. If your database has previously contained any repository content, you must remove tables from it so that a clean repository can be created. These tables need to be removed:

<code>default_binval</code>	<code>security_binval</code>
<code>default_bundle</code>	<code>security_bundle</code>
<code>default_names</code>	<code>security_names</code>

default_refs	security_refs
rep_fsenry	version_binval
rep_global_revision	version_bundle
rep_journal	version_names
rep_local_revisions	version_refs

If using Oracle, then also delete `version_seq_names_id`, `security_seq_names_id`, and `default_seq_names_id`.

5. On the seed node only, import the backed up repository content.
  - a) Start the Spectrum™ Technology Platform server (for instructions, see [Starting a Cluster](#) on page 55).
  - b) Import the contents using the `limrepo import` command, pointing to the seed node.
6. Start the remaining nodes in the cluster (for instructions, see [Starting a Cluster](#) on page 55).

## Configuring Your System

Once the Spectrum™ Technology Platform is installed and you have configured a common repository, you need to configure your instance before you can replicate it to another virtual machine. If you are not using a virtual machine environment, you will need to perform these steps on each of your Spectrum™ Technology Platform installations.

### Configure the Map File Share

To configure the map file share (a shared image folder) to Spectrum™ Technology Platform you first need a shared map image directory. To create a map file share, see [Creating a Map Image File Share on Unix/Linux](#) on page 45 or [Creating a Map Image File Share on Windows](#) on page 46.

Once a map image directory has been created, configure the map file share:

1. Modify the Mapping Service configuration by pointing to a shared image folder and load balance server. In the ImageCache change the Directory parameter to a common image directory, and change the AccessBaseURL parameter to the load balancer machine image URL.

If you are using a virtual machine environment, remember this IP address, as you must set the load balancer VM to this IP address.

For Unix/Linux installations:

```
<ImageCache>
<Directory>/<spatial server
root>/server/modules/spatial/images</Directory>
<AccessBaseURL>http://<loadbalance_IP_address>/rest/Spatial/MappingService/internal/imageCache</AccessBaseURL>

<FileExpire>30</FileExpire>
<ScanInterval>30</ScanInterval>
</ImageCache>
```

For Windows installations:

```
<ImageCache>
<Directory>\\server\Share\images</Directory>
<AccessBaseURL>http://<loadbalance_IP_address>/rest/Spatial/MappingService/internal/imageCache</AccessBaseURL>

<FileExpire>30</FileExpire>
<ScanInterval>30</ScanInterval>
</ImageCache>
```

- For Unix/Linux installations, you must set up a symbolic link to enable map images to go to the shared file system.

Create an `images` subfolder in the mounted share folder, e.g., `/mnt/<linux mount>/images`

```
cd /<spatial server root>/server/modules/spatial
rm -Rf images
ln -s /mnt/<linux mount>/images ./images
```

### Creating a Map Image File Share on Unix/Linux

The file share provides a folder to hold map images generated by Spectrum Spatial. Create a shared folder accessible to all Spectrum nodes. The file share is not required if maps are returned from the web services as Base64-encoded images.

To create a map image file share on Unix/Linux:

- Mount a shared folder on each operating system hosting Spectrum. The commands below mount a drive on a Microsoft Windows Server or network drive supporting CIFS.

```
mkdir /mnt/<linux mount>
mount -t cifs //<windows host>/<windows share> /mnt/<linux mount>-o
username=shareuser,password=sharepassword,domain=pb
```

- Set the image share to load at startup in `/etc/fstab`.

```
//<windows ip address for share>/share /path_to/mount cifs
username=server_user,password=secret,_netdev 0 0
```

### Creating a Map Image File Share on Windows

The file share provides a folder to hold map images generated by Spectrum Spatial. Create a shared folder accessible to all Spectrum nodes. The file share is not required if maps are returned from the web services as Base64-encoded images.

To create a map image file share on Windows:

1. In Windows Explorer, select the image folder you want to share.
2. Right-click, and then click **Share** or **Share with**.
3. Select the users who will be writing to the image folder. These users must have read/write privileges.

### Modifying OGC Service Configurations for Clustering

To ensure clustering works when you have both a Spectrum™ Technology Platform cluster and a Location Intelligence Module cluster, changes are required to the OGC services configuration files using Spatial Manager: From the WFS, WMS, and WMTS settings pages, change the online resource (service) URL to the IP address and port of the load balancer. See the *Spatial Manager Guide* in the Utilities section of the *Spectrum Spatial Guide* for more information.

### Modifying the Java Properties Files in All Nodes

You must change the java property file in all nodes of the cluster. To modify the java properties for Spectrum™ Technology Platform:

1. Modify the java.properties file, located in `<spectrum>/server/modules/spatial/java.properties`, to point repository.host to localhost.
2. Change the images.webapp.url and all of the service host and port numbers to point to the load balance server.

### Configuring Ports for Multiple Spectrum Instances

If you have multiple Spectrum™ Technology Platform instances on a single machine, you must change the port numbers for each instance. Change all ports in `<Spectrum root>/server/app/conf/spectrum-container.properties` to new port values that are not in use. The http port reflects the port number entered in the installer.

### Shared Spectrum Local Data

If you are using TAB file data on the file system, this data needs to be in a shared location accessible by all instances of Spectrum in the load balanced environment. It is also important to note that all named resources in the repository accessing data on the file system should point to this shared location.

Each VM or machine hosting Spectrum needs to have access to the mounted shared drive.

**Note:** Using named resources that point to database tables do not require a shared drive, as the named resources in the repository do not access the data using a file path; rather they use a named connection to the data in the database.

## Upgrading a Cluster

### Prerequisites:

- Before upgrading, be sure to read the release notes for the new version. The release notes contain important compatibility information, supported upgrade paths, and module-specific data backup recommendations.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.

This procedure is for upgrading a cluster where the Spectrum™ Technology Platform server and configuration database are installed on each node of the cluster. To upgrade a cluster, you upgrade one node at a time. The first node you upgrade is handled slightly differently than the other nodes because you must point the node to itself as a seed node since no other nodes will be running in the cluster when it starts up.

Note that these scenarios have special procedures for upgrading a cluster:

- If you have one cluster for server nodes and another cluster for configuration database nodes, see [Upgrading a Cluster with a Separated Database](#) on page 63.
- If you are upgrading a cluster for the Location Intelligence Module only, see [Upgrading a Cluster with the Location Intelligence Module](#) on page 51. If you are upgrading both Spectrum and Location Intelligence Module clusters, before shutting down all nodes also see [Upgrading a Cluster with the Location Intelligence Module](#) on page 51 for some required pre-upgrade steps.
- If you are upgrading a cluster running the Data Hub Module, see [Upgrading a Cluster with the Data Hub Module](#) on page 48.

If these scenarios do not apply to you, follow this procedure to upgrade your cluster:

1. Back up the server. For instructions on creating a backup, see the *Administration Guide*.
 

**Important:** We recommend that you create a backup before upgrading so that you can recover your flows, security settings, and other settings, if an error occurs during the upgrade process.
2. Stop all the nodes in the cluster. For more information, see [Stopping a Cluster](#) on page 56.
3. On the last node that you stopped:
  - a) Open the file `server/app/conf/spectrum-container.properties` in a text editor.
  - b) In the `spectrum.cluster.seeds` property, remove all nodes except for the current node.

**Note:** Make a note of the nodes you remove so you can add them back later.

- c) Save and close `spectrum-container.properties`.
- d) Upgrade the node. For more information, see [Upgrading a Server](#) on page 23.

**Important:** The installer will prompt you to start Spectrum™ Technology Platform after the installation completes. You must disable this option so that the server does not start automatically when the installation completes.

- e) Open the file `spectrum-container.properties` in a text editor and configure the cluster properties. For more information, see [Cluster Properties](#) on page 41. Be sure to leave `spectrum.cluster.seeds` set to only the current node's IP address or host name.
- f) Save and close `spectrum-container.properties`.
- g) Start the server.

4. Upgrade each of the other nodes, one at a time, by following this procedure:

**Important:** Follow this procedure only when upgrading nodes other than the first node. See step 3 for the procedure to upgrade the first node. Be sure you have backed up your server before proceeding.

**Important:** The next step is only applicable when upgrading from Spectrum™ Technology Platform Versions 11.1 or older.

- a) Delete this folder, if present:

```
SpectrumLocation\server\app\repository\store\databases
```

- b) Upgrade the node. For more information, see [Upgrading a Server](#) on page 23.

**Important:** The installer will prompt you to start Spectrum™ Technology Platform after the installation completes. You must disable this option so that the server does not start automatically when the installation completes.

- c) Open the file `spectrum-container.properties` in a text editor and configure the cluster properties. For more information, see [Cluster Properties](#) on page 41. Save and close the file when you are done.
- d) Start the server.

5. After you have upgraded all the nodes, go back to the first node you upgraded, open `spectrum-container.properties`, and add the seed nodes you removed from `spectrum.cluster.seeds`. You will see the message

## Upgrading a Cluster with the Data Hub Module

Prerequisites:



- Before upgrading, be sure to read the release notes for the new version. The release notes contain important compatibility information, supported upgrade paths, and module-specific data backup recommendations.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.

In a cluster that runs the Data Hub Module, each node hosts the Spectrum™ Technology Platform server as well as Data Hub Module models. When upgrading, you need to upgrade your models in addition to upgrading the Spectrum™ Technology Platform server.

The upgrade process consists of these steps:

1. Back up your models and properties files.
2. On the master server, upgrade Spectrum™ Technology Platform then upgrade your models.
3. On each non-master server, upgrade Spectrum™ Technology Platform then copy the upgraded models from the master server to the non-master server.

To upgrade a cluster that runs the Data Hub Module, follow this procedure:

1. Back up the server. For instructions on creating a backup, see the *Administration Guide*.

**Important:** We recommend that you create a backup before upgrading so that you can recover your flows, security settings, and other settings, if an error occurs during the upgrade process.

2. Open the Relationship Analysis Client and click **Manage**. Select the model you want to back up then click **Backup**.

In addition to backing up your models, back up these two property files:

- `server\modules\hub\hub.properties`
- `server\modules\db\neo4j.properties`

3. Identify which node is serving as the master server for the Data Hub Module.

- a) Open a web browser and go to:

`http://LoadBalancer:8080/jmx-console/HttpAdaptor/list`

- b) Scroll down to the **neo4j.org domain**.

You will see a set of objects for each model. The **Role** attribute in the **HighAvailability** object indicates whether a server is the master for a model.

- c) If you have more than one model and each model has a different master, you need to make one server the master of all the models. To do this, restart the cluster then open the Relationship Analysis Client using the hostname or IP address of one of the nodes rather than the load balancer. In the Relationship Analysis Client, open each model by running a query on each model. This will make the server you are connected to the master for each model.

4. Stop each non-master node in the cluster, then stop the master server last. Stop nodes one at a time rather than all at once.

**Important:** Make sure that Spectrum™ Technology Platform stops without errors. If a server does not stop properly, Data Hub Module models on the server will not open successfully after upgrading. To ensure that Spectrum™ Technology Platform stopped cleanly, examine the `SpectrumDirectory\server\app\repository\logs\wrapper.log` file for errors during shutdown.

5. Upgrade the master server.

- a) If you are upgrading from Spectrum™ Technology Platform 10.0 or later, each model directory must contain a `version.data` file. Review all the `model.ModelName` subdirectories located under `SpectrumDirectory/server/modules/hub/db` to confirm that they contain a `version.data` file. If any model directory is missing this file, copy the corresponding `version.data` file from one of the non-master nodes.
- b) Run the Spectrum™ Technology Platform installer to upgrade the master server to the new version of Spectrum™ Technology Platform.
- c) After the upgrade process finishes, the Spectrum™ Technology Platform server starts automatically. Wait for the server to finish starting completely, then stop the server.
- d) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and confirm that the `hub.neo4j.database.type` property is set to embedded:

```
hub.neo4j.database.type=embedded
```

- e) Open the file `SpectrumFolder\server\modules\hub\db\neo4j.properties` in an editor and set the `dbms.allow_format_migration` property to true:

```
dbms.allow_format_migration=true
```

- f) Start the Spectrum™ Technology Platform server.
- g) Open each model in the Relationship Analysis Client and run a query. Any query is sufficient.
- h) Stop the Spectrum™ Technology Platform server.
- i) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and set the property `hub.neo4j.database.type` to ha:

```
hub.neo4j.database.type=ha
```

- j) Compare any properties files that you backed up to the installed files and make any necessary changes. Do not overwrite new files with old files because new files may contain properties that old files do not.

6. Upgrade the non-master servers.

- a) Delete the models in the `SpectrumDirectory\server\modules\hub\db` directory.

**Warning:** Do not delete the models from the master server.

- b) On one of the non-master servers, run the Spectrum™ Technology Platform installer to upgrade it to the new version of Spectrum™ Technology Platform.

- c) After the upgrade process finishes, the Spectrum™ Technology Platform server starts automatically. Wait for the server to finish starting completely, then stop the server.
- d) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and set the property `hub.neo4j.database.type` to `ha`:

```
hub.neo4j.database.type=ha
```

- e) Compare any properties files that you backed up to the installed files and make any necessary changes. Do not overwrite new files with old files because new files may contain properties that old files do not.
  - f) Copy the `SpectrumFolder\server\modules\hub\db\model.*` directories from the master server to the non-master server.
  - g) Repeat these steps for each non-master server in the cluster.
7. Start the cluster.
- a) Start the master server, followed by non-master servers.
  - b) Ensure that each server in the cluster is functioning. Check `SpectrumFolder\server\app\repository\wrapper.log` for any errors.
  - c) While directly connected to the master server (bypassing the load balancer), open each model, one at a time, and inspect the `wrapper.log` file for errors.

## Upgrading a Cluster with the Location Intelligence Module

When a common repository database is used for clustering, these additional steps are required before and after the Spectrum™ Technology Platform upgrade process. This upgrade process must be followed even if you have a single node with a common repository database.

Before the upgrade, you must move to a local database setup; after the upgrade, you then change back to the cluster setup by pointing `repository.xml` to the external database.

**Note:** To preserve access control settings, use the Administration Utility instead of WebDAV. See the Administration section of the *Spectrum Spatial Guide* for instructions on using the Administration Utility. The `limrepo` commands in the Administration Utility were available beginning in version 11.0; if you are upgrading from a version prior to 11.0, you must use WebDAV.

1. Before upgrading Spectrum™ Technology Platform, back up the repository by following these steps.
  - a) Select a node from the cluster. This will be the seed node (see [Installing a Cluster](#) on page 36).
  - b) Back up the repository content using the Administration Utility's `limrepo export` command with ACL, pointing to the seed node.

- c) Back up the `Spectrum\server\modules\spatial\jackrabbit` folder to a location outside the installation folder.
2. Switch the common repository database to a local database (temporarily, just for upgrade purposes). Apply these steps to all nodes in the cluster.
  - a) Stop the Spectrum™ Technology Platform server on all nodes (for instructions, see [Stopping a Cluster](#) on page 56).
  - b) Delete the repository, version, workspaces folders and the `lock.properties` file (if available) from the jackrabbit folder (`Spectrum\server\modules\spatial\jackrabbit`).
  - c) Copy the contents of `repository.standalone.xml` to `repository.xml`.
  - d) Start the Spectrum™ Technology Platform server on all nodes (for instructions, see [Starting a Cluster](#) on page 55).
  - e) Import the repository content (backed up in Step 1b) into the repository using the `limrepo import` command with ACL for all nodes.
  - f) Stop the Spectrum™ Technology Platform server.
3. Follow normal procedures in [Upgrading a Cluster](#) on page 47 to upgrade Spectrum™ Technology Platform to the new version on all nodes.
4. For the seed node only, after the Spectrum™ Technology Platform upgrade is complete, back up the upgraded content by following these steps.
  - a) On the seed node, download the Administration Utility from the upgraded Spectrum™ Technology Platform server.
  - b) Back up the content from the repository using the `limrepo export` command with ACL by pointing to the seed node.
  - c) Stop the Spectrum™ Technology Platform server on all nodes (for instructions, see [Stopping a Cluster](#) on page 56).
  - d) On all nodes, back up the upgraded `Spectrum\server\modules\spatial\jackrabbit` folder to a location outside the installation folder.
5. On all nodes of Spectrum™ Technology Platform modify the configuration to specify the common database.
  - a) Copy the contents of `repository.<databaseType>.xml` to `repository.xml` located under the `server/modules/spatial/jackrabbit` folder where `<databaseType>` is the appropriate type for your database (postgres, oracle, or mssql).
  - b) In `repository.xml`:
    - Modify the DataSource section with the server host name, port, database, user, and password.
    - Modify the Cluster section to assign a distinct cluster ID, like Node1. Ensure unique IDs are assigned to every subsequent node in the cluster (for example, Node2, Node3).
    - Save the changes to `repository.xml`.
  - c) Remove these folders from the `/server/modules/spatial/jackrabbit` folder: repository, version, workspaces.

6. If your database has previously contained any repository content, you must remove tables from it so that a clean repository can be created. These tables need to be removed:

default_binval	security_binval
default_bundle	security_bundle
default_names	security_names
default_refs	security_refs
rep_fsenry	version_binval
rep_global_revision	version_bundle
rep_journal	version_names
rep_local_revisions	version_refs

If using Oracle, then also delete `version_seq_names_id`, `security_seq_names_id`, and `default_seq_names_id`.

7. On the seed node only, import the backed up repository content.
- Start the Spectrum™ Technology Platform server (for instructions, see [Starting a Cluster](#) on page 55).
  - Import the contents using the `limrepo import` command, pointing to the seed node.
8. Start the remaining nodes in the cluster (for instructions, see [Starting a Cluster](#) on page 55).

## Removing a Node from a Cluster

To remove a node from a cluster, stop the Spectrum™ Technology Platform server.

- Stop the node you want to remove:
  - On Unix or Linux, change the working directory to the Spectrum™ Technology Platform server's `bin` directory, source the setup file, then type the following command: `./server.stop`.
  - On Windows, right-click the Spectrum™ Technology Platform icon in the system tray and select **Stop Spectrum™**.

2. Open the file `server/app/conf/spectrum-container.properties` in a text editor and set `spectrum.cluster.enabled` to `false`.
3. On each of the other nodes in the cluster, open the `spectrum-container.properties` file and remove the node from the `spectrum.cluster.seeds` property.

**For Location Intelligence Module users:** If you want to keep the node standalone and able to run outside the cluster, copy back the original `repository.xml` file and remove the following folders from the `/server/modules/spatial/jackrabbit` directory for each instance of Spectrum™ Technology Platform: `repository`, `version`, `workspaces`. Restart the server and import the repository content.

## Adding Modules to a Cluster

This procedure describes how to add one or more modules to an existing cluster.

1. Stop all the Spectrum™ Technology Platform nodes in the cluster. For more information, see [Stopping a Cluster](#) on page 56. If your cluster has a separated configuration database cluster, you only need to stop the server cluster, not the configuration database cluster.

**Warning:** To prevent data loss you must stop the cluster by following the procedure described in [Stopping a Cluster](#) on page 56.

2. On any node in the cluster, install the module or modules you want to add. For more information, see the *Spectrum™ Technology Platform Installation Guide*.
3. Open this file in a text editor:

```
server/app/conf/spectrum-container.properties
```

4. In the `spectrum.cluster.seeds` property, remove all host names and IP addresses except for the one for this server. Save the host names and IP addresses so that you can re-add them later.
5. Save the file.
6. Start the server.

**Note:** Wait for the server to fully start before proceeding.

7. In the file `spectrum-container.properties`, add the host names and IP addresses that you had removed.
8. Save the file. You do not need to restart the server.
9. Install the modules on each of the other nodes in the cluster. Start each node after installing the modules on it, and wait for it to fully start before installing the modules on the next node. You do not need to modify the `spectrum.cluster.seeds` property when installing modules on subsequent nodes.

## Starting a Cluster

If all the nodes in a cluster are stopped, you must follow this procedure to start the cluster safely and avoid data loss.

1. On the last node that was stopped last, remove the seed nodes and start the server.

**Warning:** The first node that you start must be the last node that was stopped, and that node must be a seed node. Starting another node first may result in loss of data such as job history and configuration settings. If you do not know which node was stopped last, look in each node's wrapper log for the time stamp of the shutdown message. You can find the wrapper log in:

*Spectrum Location\server\app\repository\logs\wrapper.log.*

- a) Open this file in a text editor:

```
server/app/conf/spectrum-container.properties
```

- b) In the `spectrum.cluster.seeds` property, remove all host names and IP addresses except for the one for this server. Save the host names and IP addresses so that you can re-add them later.
- c) Save the file.
- d) Start the server.
- e) Wait for the Spectrum™ Technology Platform server to *completely* start.

You can tell when the Spectrum™ Technology Platform server has completely started by looking in the wrapper log: *Spectrum*

*Location\server\app\repository\logs\wrapper.log.* This message is displayed when the server is completely started:

```
Pitney Bowes Spectrum(TM) Technology Platform (Version Version
Number) Started.
```

- f) In the properties file `spectrum-container.properties`, in the `spectrum.cluster.seeds` property, add the host names or IP addresses that you had removed, separating each with a comma.
  - g) Save and close the file. You do not need to restart the server.
2. Start the other nodes in the cluster.

**Warning:** Be sure to wait for the first node to start *completely* before starting additional nodes. Starting additional nodes before the first one is started may result in loss of data.

## Stopping a Cluster

To stop an entire cluster:

1. Identify which nodes are seed nodes. To do this, open the file `SpectrumFolder/server/app/conf/spectrum-container.properties` and look at the nodes listed in the `spectrum.cluser.seeds` property.
2. Stop each Spectrum™ Technology Platform server in the cluster, making sure that the last node you stop is a seed node.
  - On Unix or Linux, change the working directory to the Spectrum™ Technology Platform server's `bin` directory, source the setup file, then type the following command: `./server.stop`.
  - On Windows, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Stop Spectrum™**.

**Warning:** To prevent loss of data the last node you stop must be a seed node.

3. Make a note of which node was the last node you stopped. You will need this information when starting up the cluster.

**Warning:** To prevent loss of data when starting the cluster, the first node you start must be the last node that was stopped, and that node must be a seed node.

## Using Enterprise Designer with a Cluster

1. Launch Enterprise Designer.
2. In the **Server name** field, enter the server name of the load balancer.
3. In the **Port** field, enter the port that you have configured the load balancer to listen on.

**Note:** Input files, output files and database resources must be on a shared drive, or file server, or some commonly-accessible location. Otherwise, all files must be loaded on each server that hosts a Spectrum™ Technology Platform server and must be located in the same path.

Once you have logged in you can use Enterprise Designer as normal. The actions you take will apply to all Spectrum™ Technology Platform instances in the cluster where you are logged in.



# 4 - Cluster with Separated Configuration Database

## In this section


---

Installing a Cluster with a Separated Configuration Database	58
Upgrading a Cluster with a Separated Database	63
Upgrading a Cluster with a Separated Database and Data Hub Module	66
Converting to a Separated Configuration Database	70
Converting from a Separated Configuration Database to a Standard Installation	72
Adding Modules to a Cluster	74

# Installing a Cluster with a Separated Configuration Database

This procedure creates two clusters: one for the server nodes and one for configuration database nodes. The nodes in the server cluster point to the servers in the configuration database cluster for their configuration data. The nodes in the configuration database cluster replicate their data between each other.

The following diagram illustrates this installation scenario:



To install a separate database repository, you first install the configuration database on servers in a cluster, then install the server on nodes in a separate cluster. At least one configuration database must be running before you can install the server.

1. Place the Spectrum™ Technology Platform installer on the server where you want to install the configuration database.
2. Double-click `installdb.exe`.
3. Follow the prompts to install the configuration database.

**Important:** When prompted with the option to start Spectrum™ Technology Platform after the installation, you must disable this option so that the database does not start automatically when the installation completes.

4. Edit the file `Database/repository/spectrum-container.properties` as described in [Cluster Properties for a Configuration Database Cluster](#) on page 62.
5. Save and close `spectrum-container.properties`.
6. Start the configuration database. To start the configuration database, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Start Spectrum™**. Alternatively, you can use the Windows Services control panel to start the configuration database by starting the **Spectrum Database** service.
7. Install the configuration database on additional servers as needed to complete the configuration database cluster.
8. Install the server cluster.
  - a) Install Spectrum™ Technology Platform on a server where you want to host a node. For instructions, see [Installing a New Server](#) on page 22.

**Important:** When installing each server select the **Server only** option in the installer and provide the host and port of one or more of the configuration database servers. You can find the port in the file

`InstallationLocation\Database\repository\spectrum-container.properties`. The port is specified in the `spectrum.repository.server.connector.bolt.port` property.

- b) If the Spectrum™ Technology Platform server is running, stop it. To stop the server, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Stop Spectrum™**.
- c) Edit the properties in the file `server/app/conf/spectrum-container.properties` as described in [Cluster Properties](#) on page 41.
- d) Save and close the `spectrum-container.properties` file.
- e) Some modules have module-specific settings that you must configure to enable the module to work in a cluster.

Module	Cluster Configuration Settings
Advanced Matching Module	<p data-bbox="745 331 1427 415">These settings configure clustering for full-text search indexes. If you do not use full-text search indexes you do not need to configure these settings.</p> <p data-bbox="745 436 1049 462">Open this file in a text editor:</p> <p data-bbox="745 483 1430 508"><code>.SpectrumFolder\server\modules\searchindex\es-container.properties</code></p> <p data-bbox="745 529 1032 554">Configure these properties:</p> <p data-bbox="745 575 1260 600"><b>es.index.default_number_of_replicas</b></p> <p data-bbox="927 621 1369 869">Enter the number of additional copies you want created for each search index. This number should be the number of nodes in your cluster minus 1. For example, if your cluster has five nodes, you would enter "4" in this property.</p> <p data-bbox="745 890 1243 915"><b>es.index.default_number_of_shards</b></p> <p data-bbox="927 936 1369 1108">Enter the number of shards you want your index to have in the distributed environment. The more nodes that are in your cluster, the higher this number should be.</p> <p data-bbox="745 1129 1427 1192">Save and close <code>es-container.properties</code> when you are done editing these properties.</p> <p data-bbox="829 1213 1409 1388"><b>Note:</b> Search indexes created prior Spectrum™ Technology Platform 10.0 do not support clustering. To enable clustering for indexes created prior to the 10.0 release, you must recreate the search index using the 10.0 API after modifying the <code>es-container.properties</code> file.</p>

Module	Cluster Configuration Settings
Data Hub Module	<p>Open this file in a text editor:</p> <p><i>SpectrumFolder</i>\server\modules\hub\hub.properties</p> <p>Configure these properties:</p> <p><b>hub.models.path.base</b></p> <p>Specifies the folder where models are stored. By default, each model is placed in a subdirectory under the <i>SpectrumFolder</i>\server\modules\hub\db folder. If you want to store models in a different location, uncomment this property and specify the folder where you want to store models.</p> <p><b>hub.neo4j.database.type</b></p> <p>Change the value of this property to ha. The default value embedded is for non-clustered installations.</p> <p><b>hub.servers.per.cluster</b></p> <p>Uncomment this line. Set the value of this property to the number of Spectrum™ Technology Platform servers in the cluster.</p> <p>Save and close <i>hub.properties</i> when you are done editing these properties.</p> <p>The <i>SpectrumFolder</i>\server\modules\hub\db\neo4j.properties controls how the graph databases are configured, using Neo4j Enterprise. This file is used as a template for each model. If needed, each model can be configured separately by placing a copy of this property file into the store directory for that model.</p>

- f) Start the server. To start the server, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.
  - g) Repeat this procedure to install additional nodes in the server cluster.
9. After installing all the nodes in the server cluster, go back to the first node you installed in the server cluster and add the other nodes as seed nodes.
- a) On the first node you installed, open the properties file *server/app/conf/spectrum-container.properties*.

- b) In the property `spectrum.cluster.seeds`, add the host name or IP address of the other nodes in the cluster, separating each with a comma.
- c) Save and close the `spectrum-container.properties` file. You do not need to restart the server.

## Cluster Properties for a Configuration Database Cluster

A configuration database cluster is a cluster where each node contains the configuration database only, and not the server. If you are setting up a cluster where the server and configuration database are installed together on each node, or are setting up a server-only cluster, see [Cluster Properties](#) on page 41.

The settings for a configuration database cluster are located in this properties file:

`Database\repository\spectrum-container.properties`

This table describes each property:

Property	Description
<code>spectrum.cluster.enabled</code>	Set this to true.
<code>spectrum.cluster.name</code>	<p>If this is the first node in the cluster, set this to any name you want to give to the configuration database cluster. Be sure that the name is unique if you have multiple clusters.</p> <p>If you are adding a node to an existing cluster, set this to the name of the configuration database cluster that you want this node to join.</p>
<code>spectrum.cluster.address</code>	Specify the node's own IP address.

Property	Description
<code>spectrum.cluster.seeds</code>	<p>If you are setting up the first node in the cluster, or if this is the first node you are starting after having stopped the cluster, specify only the host name or IP address of this server. This effectively points this node to itself as a seed node, which is necessary in order for it to be able to start as the first node in the cluster.</p> <p>If this is not the first node in the cluster, set this to the host name or IP address of the Spectrum™ Technology Platform server whose configuration will be replicated on this node when it joins the cluster, resulting in synchronized configuration. You can specify multiple seed nodes by separating each with a comma. When starting up, the node will attempt to access each seed node in the order listed. If none of the seed nodes can be reached, the node will not join the cluster.</p> <p><b>Tip:</b> We recommend that you specify multiple seed nodes so that if one seed node is down others can be used to allow nodes to join the cluster. We also recommend that you specify the same seed nodes in the same order on all nodes in the cluster.</p>
<code>spectrum.cluster.nodeID</code>	<p>Set this to an integer value to use as the ID for this node. The ID must be an integer and must be unique among all nodes in the database cluster. For example, you could set the node ID for the first node to 1, the second node's node ID to 2, and the third node's node ID to 3.</p>

## Upgrading a Cluster with a Separated Database

### Prerequisites:

- Before upgrading, be sure to read the release notes for the new version. The release notes contain important compatibility information, supported upgrade paths, and module-specific data backup recommendations.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.

This procedure describes how to upgrade Spectrum™ Technology Platform when you have separated the configuration database from the server. To upgrade an environment that has a separated configuration database, you first upgrade the configuration database cluster, then the server cluster.

1. Back up the server. For instructions on creating a backup, see the *Administration Guide*.

**Important:** We recommend that you create a backup before upgrading so that you can recover your flows, security settings, and other settings, if an error occurs during the upgrade process.

2. Back up module-specific data for any of these modules if you have them installed.

Module	Items to Back Up
Advanced Matching Module, Data Normalization Module, and Universal Name Module	<p>Back up the contents of these subfolders located in <i>SpectrumLocation/server/modules</i>:</p> <ul style="list-style-type: none"> <li>• cdqdb</li> <li>• lucene</li> <li>• matcher</li> <li>• parser</li> <li>• searchindex</li> <li>• tables</li> <li>.</li> </ul>
Data Hub Module	<p>Open the Relationship Analysis Client and click <b>Manage</b>. Select the model you want to back up then click <b>Backup</b>.</p> <p>In addition to backing up your models, back up these two property files:</p> <ul style="list-style-type: none"> <li>• server\modules\hub\hub.properties</li> <li>• server\modules\db\neo4j.properties</li> </ul>
Location Intelligence Module	<p>Back up your named resources, data, and configuration files.</p>

3. Stop all the nodes in the server cluster then stop all the nodes in the configuration database cluster. Make a note of the last node that you stop in the configuration database cluster. You must start this node first after upgrading. For instructions on stopping a cluster, see [Stopping a Cluster](#) on page 56.
4. On the *last* node that you shut down in the configuration database cluster, execute `installdb.exe`. The installer upgrades the configuration database.

**Warning:** The first node that you upgrade must be the last node that was stopped. This is because on some operating systems the configuration database will start automatically at the end of the upgrade process. If the first node that starts is not the last node that was stopped, data such as job history and configuration settings may be lost. If you do not know which node was stopped last, look in each node's wrapper log for the time stamp of the shutdown message. You can find the wrapper log in: *Spectrum Location\Database\repository\logs\wrapper.log*.



**Important:** When prompted with the option to start Spectrum™ Technology Platform after the installation, you must disable this option so that the database does not start automatically when the installation completes.

5. After the upgrade is complete, the configuration database starts up automatically. Verify that the configuration database is fully started before continuing by opening the log file `SpectrumInstallationLocation\Database\repository\logs\wrapper.log` and looking for the message `Started`.

**Important:** Do not attempt to stop the server until after it has fully started for the first time. Stopping the server before it performs an initial startup can cause your installation to become unusable.

6. Stop the configuration database. To stop the configuration database, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Stop Spectrum™**. Alternatively, you can use the Windows Services control panel to stop the configuration database by stopping the **Spectrum Database** service.
7. Configure clustering for the database cluster.
  - a) Edit the file `Database/repository/spectrum-container.properties` as described in [Cluster Properties for a Configuration Database Cluster](#) on page 62.
  - b) Save and close the `spectrum-container.properties` file.
  - c) Start the *last* node that was stopped in the configuration database cluster. To start the configuration database, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Start Spectrum™**. Alternatively, you can use the Windows Services control panel to start the configuration database by starting the **Spectrum Database** service.
  - d) After the upgraded configuration database is fully started, repeat the previous steps to upgrade each of the remaining servers in the configuration database cluster and start each of them.
8. Upgrade each node in the server cluster. For more information, see [Upgrading a Cluster](#) on page 47.

**Important:** When installing each server select the **Server only** option in the installer and provide the host and port of one or more of the configuration database servers. You can find the port in the file

`InstallationLocation\Database\repository\spectrum-container.properties`. The port is specified in the `spectrum.repository.server.connector.bolt.port` property.

**Note:** Any job or subflow stored in the system during a server upgrade is marked as exposed to provide the same behavior for those jobs and subflows as before the upgrade. Any job or subflow that is exported prior to the upgrade will not be exposed. Therefore, when importing these jobs or subflows back into the system, you must manually expose the imported job or subflow.

Some modules have post-upgrade steps you need to perform.

## Data Hub Module

Open this file in a text editor:

```
server/modules/hub/neo4j.properties
```

and set the property `allow_store_upgrade` property to true. The purpose of this property is to protect against unintentional and irreversible store upgrades. Setting this property to "true" indicates that you understand the ramifications of proceeding with an upgrade and have taken the necessary precautions before proceeding.

Restart the Spectrum™ Technology Platform server. The server will upgrade each model. Examine the file `server/app/repository/logs/wrapper.log` for errors or warning messages. Once all models have been upgraded, go back to the `hub.properties` file and comment out the `allow_store_upgrade` property.

## Upgrading a Cluster with a Separated Database and Data Hub Module

### Prerequisites:

- Before upgrading, be sure to read the release notes for the new version. The release notes contain important compatibility information, supported upgrade paths, and module-specific data backup recommendations.
- Apply all the latest updates available for your operating system, especially those that resolve issues with Java.

This procedure describes how to upgrade Spectrum™ Technology Platform when you have separated the configuration database from the server and you have the Data Hub Module installed. The upgrade process consists of these steps:

1. Stop the server cluster.
2. Stop the configuration database cluster.
3. Upgrade the last node that was stopped in the configuration database cluster.
4. Upgrade the other nodes in the configuration database cluster.
5. Upgrade the server acting as the Data Hub Module master in the server cluster.
6. Upgrade the non-master servers in the server cluster.

To upgrade a cluster with a separated configuration database and the Data Hub Module, follow this procedure:

1. Back up the server. For instructions on creating a backup, see the *Administration Guide*.

**Important:** We recommend that you create a backup before upgrading so that you can recover your flows, security settings, and other settings, if an error occurs during the upgrade process.

2. Open the Relationship Analysis Client and click **Manage**. Select the model you want to back up then click **Backup**.

In addition to backing up your models, back up these two property files:

- `server\modules\hub\hub.properties`
- `server\modules\db\neo4j.properties`

3. Identify which node is the serving as the master server for the Data Hub Module.

- a) Open a web browser and go to:

`http://LoadBalancer:8080/jmx-console/HttpAdaptor/list`

- b) Scroll down to the **neo4j.org domain**.

You will see a set of objects for each model. The **Role** attribute in the **HighAvailability** object indicates whether a server is the master for a model.

- c) If you have more than one model and each model has a different master, you need to make one server the master of all the models. To do this, restart the cluster then open the Relationship Analysis Client using the hostname or IP address of one of the nodes rather than the load balancer. In the Relationship Analysis Client, open each model by running a query on each model. This will make the server you are connected to the master for each model.

4. Stop all the non-master nodes in the server cluster then stop the master server last. Stop nodes one at a time rather than all at once.

**Important:** Make sure that Spectrum™ Technology Platform stops without errors. If a server does not stop properly, Data Hub Module models on the server will not open successfully after upgrading. To ensure that Spectrum™ Technology Platform stopped cleanly, examine the `SpectrumDirectory\server\app\repository\logs\wrapper.log` file for errors during shutdown.

5. Stop all the nodes in the configuration database cluster. Make a note of the last node that you stop in the configuration database cluster. You must start this node first after upgrading.
6. On the *last* node that you shut down in the configuration database cluster, execute `installdb.exe`. The installer upgrades the configuration database.

**Warning:** The first node that you upgrade must be the last node that was stopped. This is because on some operating systems the configuration database will start automatically at the end of the upgrade process. If the first node that starts is not the last node that was stopped, data such as job history and configuration settings may be lost. If you do not know which node was stopped last, look in each node's wrapper log for the time stamp of the shutdown message. You can find the wrapper log in: `Spectrum Location\server\app\repository\logs\wrapper.log`.

7. After the upgrade process finishes, wait for the server to start, then stop the server.

You can see when the server has started up by opening the log file `<Spectrum Installation Location>\server\app\repository\logs\wrapper.log` and looking for this message:

```
INFO [Server] Pitney Bowes Spectrum(TM) Technology Platform Database
      (Version version build) Started
```

**Important:** Do not attempt to stop the server until after it has fully started for the first time. Stopping the server before it performs an initial startup can cause your installation to become unusable.

8. Configure clustering for the database cluster.
  - a) Edit the file `server/app/conf/spectrum-container.properties` as described in [Cluster Properties for a Configuration Database Cluster](#) on page 62.
  - b) Save and close the `spectrum-container.properties` file.
  - c) Start the *last* node that was stopped in the configuration database. To start the configuration database, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Start Spectrum™**. Alternatively, you can use the Windows Services control panel to start the configuration database by starting the **Spectrum Database** service.

**Warning:** The first node that you start must be the last node that was stopped, and that node must be a seed node. Starting another node first may result in loss of data such as job history and configuration settings. If you do not know which node was stopped last, look in each node's wrapper log for the time stamp of the shutdown message. You can find the wrapper log in: `Spectrum Location\server\app\repository\logs\wrapper.log`.

- d) After the upgraded configuration database is fully started, repeat the previous steps to upgrade each of the remaining servers in the configuration database cluster and start each of them.
9. Upgrade the Data Hub Module master server in the server cluster.
  - a) If you are upgrading from Spectrum™ Technology Platform 10.0 or later, each model directory must contain a `version.data` file. Review all the `model.ModelName` subdirectories located under `SpectrumDirectory/server/modules/hub/db` to confirm that they contain a `version.data` file. If any model directory is missing this file, copy the corresponding `version.data` file from one of the non-master nodes.
  - b) Run the Spectrum™ Technology Platform installer to upgrade the master server to the new version of Spectrum™ Technology Platform.
  - c) After the upgrade process finishes, the Spectrum™ Technology Platform server starts automatically. Wait for the server to finish starting completely, then stop the server.
  - d) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and confirm that the `hub.neo4j.database.type` property is set to embedded:

```
hub.neo4j.database.type=embedded
```

- e) Open the file `SpectrumFolder\server\modules\hub\db\neo4j.properties` in an editor and set the `dbms.allow_format_migration` property to true:

```
dbms.allow_format_migration=true
```

- f) Start the Spectrum™ Technology Platform server.  
 g) Open each model in the Relationship Analysis Client and run a query. Any query is sufficient.  
 h) Stop the Spectrum™ Technology Platform server.  
 i) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and set the property `hub.neo4j.database.type` to ha:

```
hub.neo4j.database.type=ha
```

- j) Compare any properties files that you backed up to the installed files and make any necessary changes. Do not overwrite new files with old files because new files may contain properties that old files do not.

#### 10. Upgrade the Data Hub Module non-master servers in the server cluster.

**Important:** When installing each server select the **Server only** option in the installer and provide the host and port of one or more of the configuration database servers. You can find the port in the file

`InstallationLocation\Database\repository\spectrum-container.properties`. The port is specified in the `spectrum.repository.server.connector.bolt.port` property.

- a) Delete the models in the `SpectrumDirectory\server\modules\hub\db` directory.

**Warning:** Do not delete the models from the master server.

- b) On one of the non-master servers, run the Spectrum™ Technology Platform installer to upgrade it to the new version of Spectrum™ Technology Platform.  
 c) After the upgrade process finishes, the Spectrum™ Technology Platform server starts automatically. Wait for the server to finish starting completely, then stop the server.  
 d) Open the file `SpectrumFolder\server\modules\hub\hub.properties` in an editor and set the property `hub.neo4j.database.type` to ha:

```
hub.neo4j.database.type=ha
```

- e) Compare any properties files that you backed up to the installed files and make any necessary changes. Do not overwrite new files with old files because new files may contain properties that old files do not.  
 f) Copy the `SpectrumFolder\server\modules\hub\db\model.*` directories from the master server to the non-master server.  
 g) Repeat these steps for each non-master server in the cluster.

#### 11. Start the cluster.

- a) Start the master server, followed by non-master servers.

- b) Ensure that each server in the cluster is functioning. Check `SpectrumFolder\server\app\repository\wrapper.log` for any errors.
- c) While directly connected to the master server (bypassing the load balancer), open each model, one at a time, and inspect the `wrapper.log` file for errors.

## Converting to a Separated Configuration Database

Converting an existing Spectrum™ Technology Platform installation to a separated configuration database enables you to take advantage of the improved scalability of a separated configuration database. When you convert to a separated configuration database, your existing installation is converted from one where the configuration database is part of the server to one where the configuration database is in a separate cluster.

At a high level, this is the conversion process:

- Stop your existing Spectrum™ Technology Platform server.
- Set up the new configuration database cluster:
  - Install the separate configuration database software on a new server.
  - Copy your existing configuration database to the new server.
  - Configure clustering and start the configuration database cluster.
- Install the server-only cluster and start it up.

**Note:** This procedure applies both to converting a single server to a separated configuration database, and converting a cluster to a separated configuration database.

To convert to a separated configuration database:

1. Back up module-specific data for any of these modules if you have them installed.

Module	Items to Back Up
Advanced Matching Module, Data Normalization Module, and Universal Name Module	Back up the contents of these subfolders located in <code>SpectrumLocation/server/modules</code> : <ul style="list-style-type: none"> <li>• <code>cdqdb</code></li> <li>• <code>lucene</code></li> <li>• <code>matcher</code></li> <li>• <code>parser</code></li> <li>• <code>searchindex</code></li> <li>• <code>tables</code></li> </ul>

Module	Items to Back Up
Data Hub Module	<p>Open the Relationship Analysis Client and click <b>Manage</b>. Select the model you want to back up then click <b>Backup</b>.</p> <p>In addition to backing up your models, back up these two property files:</p> <ul style="list-style-type: none"> <li>• <code>server\modules\hub\hub.properties</code></li> <li>• <code>server\modules\db\neo4j.properties</code></li> </ul>
Location Intelligence Module	Back up your named resources, data, and configuration files.

- If the server you are converting is running Spectrum™ Technology Platform 11.0 SP1 or earlier, you must upgrade to the latest version of Spectrum™ Technology Platform before converting from a standard installation to a separated configuration database. For more information, see [Upgrading a Server](#) on page 23 (for upgrading a single server) or [Upgrading a Cluster](#) on page 47 (for upgrading a cluster).
- Stop the server. If you have a clustered installation, stop the cluster.
- Install the configuration database to a new server.
  - Place the Spectrum™ Technology Platform installer on the machine where you want to install the configuration database. This must be a different machine from the one where you have your existing Spectrum™ Technology Platform server installed.
  - Double-click `installdb.exe`.
  - Follow the prompts to install the configuration database.

**Important:** When prompted with the option to start Spectrum™ Technology Platform after the installation, you must disable this option so that the database does not start automatically when the installation completes.
  - Copy the `Database\repository\data\databases` folder from your existing server to the server where you installed the separate configuration database. Replace the existing folder.
  - Configure the cluster properties for the database cluster by editing the file `Database\repository\spectrum-container.properties` as described in [Cluster Properties for a Configuration Database Cluster](#) on page 62.
  - Save and close the `spectrum-container.properties` file.
  - Start the configuration database. To start the configuration database, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Start Spectrum™**. Alternatively, you can use the Windows Services control panel to start the configuration database by starting the **Spectrum Database** service.
  - Install the configuration database on additional servers as needed to complete the configuration database cluster.
- Install the server.

- a) (Optional) If you are upgrading to a new version and you want to use the same machine to host the upgraded server as hosted the existing server, uninstall the existing server of Spectrum™ Technology Platform.
- b) Install the server cluster. For more information, see [Installing a Cluster](#) on page 36.

**Important:** When installing each server select the **Server only** option in the installer and provide the host and port of one or more of the configuration database servers. You can find the port in the file

*InstallationLocation*\Database\repository\spectrum-container.properties.  
The port is specified in the `spectrum.repository.server.connector.bolt.port` property.

## Converting from a Separated Configuration Database to a Standard Installation

If you have a cluster that consists of separate clusters for the server and for the configuration database, you can convert your installation to a standard installation where the server and configuration database are installed together on the same server.

1. Back up module-specific data for any of these modules if you have them installed.

Module	Items to Back Up
Advanced Matching Module, Data Normalization Module, and Universal Name Module	Back up the contents of these subfolders located in <i>SpectrumLocation/server/modules</i> : <ul style="list-style-type: none"> <li>• cdqdb</li> <li>• lucene</li> <li>• matcher</li> <li>• parser</li> <li>• searchindex</li> <li>• tables</li> <li>•</li> </ul>



Module	Items to Back Up
Data Hub Module	<p>Open the Relationship Analysis Client and click <b>Manage</b>. Select the model you want to back up then click <b>Backup</b>.</p> <p>In addition to backing up your models, back up these two property files:</p> <ul style="list-style-type: none"> <li>• <code>server\modules\hub\hub.properties</code></li> <li>• <code>server\modules\db\neo4j.properties</code></li> </ul>
Location Intelligence Module	Back up your named resources, data, and configuration files.

2. Stop all the nodes in the server cluster then stop all the nodes in the configuration database cluster.
3. The configuration database must be of the same version of Spectrum™ Technology Platform as the server you are converting to. If the configuration database is from an older version, upgrade the configuration database to the same version of Spectrum™ Technology Platform as the version you want to use for the standard server. On the *last* node that you shut down in the configuration database cluster, execute `installdb.exe`. The installer upgrades the configuration database.

**Warning:** The node that you upgrade must be the last node that was stopped. This is so that data such as job history and configuration settings are not lost. If you do not know which node was shut down last, look in each node's wrapper log for the time stamp of the shutdown message.

You can find the wrapper log in: *Spectrum*

`Location\server\app\repository\logs\wrapper.log`.

4. After the upgrade process finishes, wait for the server to start, then stop the server.

You can see when the server has started up by opening the log file

`SpectrumInstallationLocation\Database\repository\logs\wrapper.log` and looking for the message `Started`.

**Important:** Do not attempt to stop the server until after it has fully started for the first time. Stopping the server before it performs an initial startup can cause your installation to become unusable.

5. Install a new server. For instructions, see [Installing a New Server](#) on page 22.

**Note:** When prompted, be sure to select **Standard Installation**, not **Server only**.

6. Stop the server.
7. Copy the `SpectrumLocation\Database\repository\data\databases` folder from the last configuration database server you stopped to the new server, replacing the existing folder.
8. Start the server.

## Adding Modules to a Cluster

This procedure describes how to add one or more modules to an existing cluster.

1. Stop all the Spectrum™ Technology Platform nodes in the cluster. For more information, see [Stopping a Cluster](#) on page 56. If your cluster has a separated configuration database cluster, you only need to stop the server cluster, not the configuration database cluster.

**Warning:** To prevent data loss you must stop the cluster by following the procedure described in [Stopping a Cluster](#) on page 56.

2. On any node in the cluster, install the module or modules you want to add. For more information, see the *Spectrum™ Technology Platform Installation Guide*.
3. Open this file in a text editor:

```
server/app/conf/spectrum-container.properties
```

4. In the `spectrum.cluster.seeds` property, remove all host names and IP addresses except for the one for this server. Save the host names and IP addresses so that you can re-add them later.
5. Save the file.
6. Start the server.

**Note:** Wait for the server to fully start before proceeding.

7. In the file `spectrum-container.properties`, add the host names and IP addresses that you had removed.
8. Save the file. You do not need to restart the server.
9. Install the modules on each of the other nodes in the cluster. Start each node after installing the modules on it, and wait for it to fully start before installing the modules on the next node. You do not need to modify the `spectrum.cluster.seeds` property when installing modules on subsequent nodes.

# 5 - Spectrum Databases

After you have installed the server you need to install the databases that support the module(s) you have installed. Databases provide the information that Spectrum™ Technology Platform modules use to process data, such as postal address data, name data, or geospatial data. For example, if you have installed the Enterprise Geocoding Module, you will need to install databases that contain geospatial data; if you have installed the Universal Addressing Module, you will need to install databases that contain postal data.

## In this section

---

Installing a Spectrum Database	76
Installing the Address Now Module Database	77
Installing the Advanced Matching Module Database	77
Installing Data Normalization Module Databases	78
Installing Enterprise Geocoding Module Databases	80
Installing Enterprise Routing Module Databases	83
Installing Enterprise Tax Module Databases	83
Installing GeoEnrichment Module Databases	87
Installing Global Addressing Module Databases	88
Installing Global Geocoding Module Databases	90
Installing the Global Sentry Module Database	93
Installing Location Intelligence Module Databases	95
Installing Universal Addressing Module Databases	96
Installing Universal Name Module Databases	98
Using the Database Silent Installer	99

## Installing a Spectrum Database

Spectrum databases contain reference data from trusted data providers that is used to enhance and validate your data. For example, to perform address validation, Spectrum™ Technology Platform uses official address data from the postal authority to compare your address to the official address. Other types of processing that use Spectrum databases include geocoding, location intelligence functions like point-in-polygon or travel directions, and tax jurisdiction assignment for a given address.

We update Spectrum databases periodically to provide you with the most up-to-date data from third-party data providers. Database updates occur independently from software updates, in some cases quarterly or even monthly. When a database update is available you will receive an email notification that includes a link to download the updated database. You should install it as soon as possible so that you are using the most accurate data available.

Beginning with Spectrum™ Technology Platform version 12.1, some databases have changed to support a simpler installation and configuration process. This includes international data that is consumed by [Enterprise Geocoding Module](#), [Global Geocoding Module](#) and [Global Address Module](#). Refer to those topics for more information.

1. Download your licensed SPD files from the Pitney Bowes eStore using the link provided in the release announcement or welcome email.
2. Place the .spd files in:

```
SpectrumLocation/server/app/dataimport
```

The SPD file is automatically extracted to:

```
SpectrumLocation/server/app/repository/datastorage
```

Once the database has been extracted to the `datastorage` folder, it is installed and you can define it as a database resource using Management Console. Find more information about Management Console in the Administration Guide.

You can modify the Spectrum database installation process if needed:

- You can change the location of the data import directory by altering the **platform** property in the `<SpectrumLocation>/server/app/conf/dataimportdirectories.properties` file.
- You can change the location of the data storage folder by altering the **spectrum.data.manager.storage.directory** property in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file. Consider creating a storage folder outside of Spectrum so it will not be deleted when you uninstall Spectrum.
- By default, the SPD files are deleted after the files are extracted or when Spectrum is uninstalled. However, you can archive SPD files by setting the **spectrum.data.manager.archive.data** property to "true" in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file.

- With any change to properties files, you must stop and restart the Spectrum server.

## Installing the Address Now Module Database

1. Copy the `liclcs.sbi` license file provided by Pitney Bowes into the following directory:  
<SpectrumPlatformLocation>\server\modules\anow\license.
2. Make sure no applications are running.
3. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Stop Server**.
4. Insert the database DVD containing the database(s) you want to install.

**Note:** You must install the Postal databases if you want to use the Enhanced databases.

5. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Address Now Module > Address Now Data Loader**.
6. The installation wizard guides you through the rest of the process.

**Note:** The installation location for the Address Now directory defaults to <SpectrumPlatformLocation>\server\modules\anow. Do not change this path or the database will not install correctly.

**Note:** When prompted for the location of the Installation Media Directory, be sure to select the directory on the database DVD that contains the `kbase` folder.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

7. When the Data Loader is finished, start the Address Now server by going to **Control Panel > Administrative Tools > Services**. Right-click the Address Now Server service and select Start.
8. After the database installed, start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows system tray and select **Start Spectrum™**.

## Installing the Advanced Matching Module Database

The Advanced Matching Module provides a load utility to install databases. The database files that you install depend on the databases you have licensed.

**Note:** To install the Advanced Matching Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Stop Server**.
3. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

4. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Universal Name and Advanced Matching Modules > Database Load Utility**.
5. Follow the prompts during the rest of the installation process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

6. Open the file `<SpectrumDirectory>\server\bin\wrapper\wrapper.conf` in a text editor.
7. Increase the Java settings for initial heap size (`wrapper.java.initmemory`) and maximum heap size (`wrapper.java.maxmemory`) to reflect the total amount of memory required for the Arabic Plus Pack and Asian Plus Pack.
  - Arabic Plus Pack: 5.5 GB
  - Asian Plus Pack - Chinese: 32 MB
  - Asian Plus Pack - Japanese: 1.6 GB
  - Asian Plus Pack - Korean: 8 MB
  - Core Names: 1.1 GB
8. Save and close `wrapper.conf`.
9. Start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.

## Installing Data Normalization Module Databases

The Data Normalization Module provides a load utility to install databases for the Advanced Transformer, Open Parser, and Table Lookup components. The database files that you install depend on the databases you have licensed. Use this list of database tables to determine which files you should download and install. For more information on the tables contained in each database, refer to the reference documentation for each component.

Stage	Available Databases
Advanced Transformer	Data Normalization Module - Base Tables
Open Parser	<ul style="list-style-type: none"> <li>• Data Normalization Module - Base Tables</li> <li>• Core Names Database</li> <li>• Company Names Database</li> <li>• Arabic Plus Pack</li> <li>• Asian Plus Pack</li> </ul>
Table Lookup	<ul style="list-style-type: none"> <li>• Data Normalization Module - Base Tables</li> <li>• Core Names Database</li> <li>• Arabic Plus Pack</li> <li>• Asian Plus Pack</li> <li>• ZREPLACE (Used by the SAP Module for French address validation)</li> </ul>

**Note:** To install the Data Normalization Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Stop Server**.
3. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

4. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Data Normalization Module > Database Load Utility**.
5. Follow the prompts during the rest of the installation process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

6. Start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.

## Installing Enterprise Geocoding Module Databases

This module has several databases. You may have one or more of these, depending on the features you have licensed.

### International Geocoding Databases

International geocoding databases contain the data necessary to perform geocoding and reverse geocoding for locations outside the U.S. Each country has its own database, and some countries have optional databases that provide enhanced geocoding.

**Note:** Do not install geocoding databases on a network drive. Doing so can cause performance problems.

**Note:** To install the Enterprise Geocoding Module databases on Windows Server 2008 you need administrator privileges.

1. Download your licensed SPD files from the Pitney Bowes eStore using the link provided in the release announcement or welcome email.
2. Place the `.spd` files in:

```
SpectrumLocation/server/app/dataimport
```

The SPD file is automatically extracted to:

```
SpectrumLocation/server/app/repository/datastorage
```

Once the database has been extracted to the `datastorage` folder, it is installed and you can define it as a database resource using Management Console. Find more information about Management Console in the Administration Guide.

You can modify the Spectrum database installation process if needed:

- You can change the location of the data import directory by altering the **platform** property in the `<SpectrumLocation>/server/app/conf/dataimportdirectories.properties` file.
- You can change the location of the data storage folder by altering the **spectrum.data.manager.storage.directory** property in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file. Consider creating a storage folder outside of Spectrum so it will not be deleted when you uninstall Spectrum.
- By default, the SPD files are deleted after the files are extracted or when Spectrum is uninstalled. However, you can archive SPD files by setting the **spectrum.data.manager.archive.data** property



to "true" in the Data Manager settings section of the

<SpectrumLocation>/server/app/conf/spectrum-container.properties file.

- With any change to properties files, you must stop and restart the Spectrum server.

### AUS G-NAF

If you installed the Australia Geocoded National Address File (G-NAF), you must specify the GNAF123 and GNAF456 as separate paths but in the same database resource in the Management Console. GNAF123 contains the point-level dictionary. This has the highest precision of geocoding (characterized by Reliability Level 1, 2, or 3.) GNAF456 contains the remainder of address information in G-NAF that does not meet high precision geocoding criteria (characterized by Reliability Level 4, 5, or 6.) We recommend that you use both databases to validate the existence of addresses but only use GNAF123 for parcel-level geocoding. If you do not require parcel-level geocodes you can use GNAF456 for geocoding.

## U.S. Geocoding Databases

The U.S. geocoding databases contain the spatial data necessary to perform address standardization and geocoding. You must install at least one of these databases.

- **Centrus Enhanced Geocoding**—This database consists of TIGER data provided by the U.S. Geological Survey and address data provided by the U.S. Postal Service.
- **TomTom Geocoding**—This database provides more up-to-date data than the Centrus Enhanced Geocoding database. It requires an additional license. The data is provided by TomTom, a third-party provider of spatial data, and postal data from the U.S. Postal Service.
- **NAVTEQ Geocoding**—This database provides more up-to-date data than the Centrus Enhanced Geocoding database. It requires an additional license. NAVTEQ data is provided by NAVTEQ, a third-party provider of spatial data. For more information about these databases, contact your sales representative.
- **ZIP + 4 Centroid**—This database provides only address standardization and ZIP + 4 centroid matching. It does not provide street-level matching.

These databases use proprietary files called GSD files. For ZIP Code centroid matching, the file us.Z9 contains all the centroid info for all states and normally has a z9 extension.

Each geocoding database has an optional Statewide Intersections Index. The Statewide Intersection Index is designed to enable fast intersection identification on a statewide basis. For example, the Statewide Intersection Index will allow the database to search for "1st and Main St, CO" and return a list of possible matches in Colorado more quickly than searching the entire geocoding database for each instance of the intersection.

**Note:** To install the Enterprise Geocoding Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.

2. Download the database from the Pitney Bowes Software eStore using the link provided in the release announcement or welcome email. You can also download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).
3. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
4. Run `DataSets.exe`. The installation wizard guides you through the rest of the process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

5. After you install the database files, use the Database Resource tool in the Management Console to define the database as a resource. For more information, see the *Administration Guide*.

## Points Databases (U.S. Only)

Points databases contain data for locating the center of a parcel. These databases provides enhanced geocoding accuracy for internet mapping, property and casualty insurance, telecommunications, utilities, and others.

- **Master Location Data**—This database provides the best available address point location for every mailable and deliverable address in the United States.
- **Centrus Points**—This database contains the data necessary to locate the center of a parcel or building. It does not contain assessor's parcel number (APN) or elevation data.
- **Centrus Elevation**—This database contains the same data as Centrus Points, plus elevation data.
- **Centrus Enhanced Points**—This database contains the same data as Centrus Points, plus APN data.
- **Centrus Premium Points**—This database contains the same data as Centrus Points, plus both APN and elevation data.
- **TomTom Points Database**—The data in this database is provided by TomTom, a third-party provider of spatial data.
- **NAVTEQ Points**—This database is provided by NAVTEQ, a third-party data provider. It contains data used to locate addresses at the center of the actual building footprint or parcel.

**Note:** To install the Enterprise Geocoding Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the Pitney Bowes web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

3. Run `Setup.exe`. The installation wizard guides you through the rest of the process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

4. After you install the database files, use the Database Resource tool in the Management Console to define the database as a resource. For more information, see *Spectrum™ Technology Platform Administration Guide*.

## Early Warning System (U.S. Only)

The USPS provides free Early Warning System (EWS) data to prevent matching errors due to the age of the address information in the .gsd files. The USPS creates a new EWS data set each week that you can download from the USPS website ([ribbs.usps.gov](http://ribbs.usps.gov)).

To install the Early Warning System (EWS) database rename the database file from OUT to EWS.txt and place it in the same folder as the primary database.

## Installing Enterprise Routing Module Databases

1. Make sure no applications are running.
2. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the technical support web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

3. Run `dbloader.exe`.
4. Follow the prompts during the rest of the installation process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

## Installing Enterprise Tax Module Databases

Depending on the features you have licensed, you need to install one or more of these databases.

## Database Compatibility

The Enterprise Tax Module version 9.0 SP2 and later uses a different data format than previous releases. You must download and install the **GeoTAX/Enterprise Tax Premium database** for use in this version. The GeoTAX/Enterprise Tax Premium database is not compatible with any releases prior to version 9.0 SP2.

## Downloading Database Files

**Note: Prior to downloading the data files:** If you have previously installed database files, you should back up those files and delete any copies of the .gdi, .gsd, gsi, .gsl, .gsu, .gsz, .gsx, .z9, .dir, .las and .los files in the data install directory.

### *Downloading from the eStore*

Use the link in your welcome email to download the zip file. Extract the files and make note of the directory where you save the files.

### *Downloading from the Technical Support Web Site*

Download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support). The data file will be downloaded as a .zip file. Extract the files and make note of the directory where you save the files.

## Downloading Florida Format Files

You can obtain the Florida format files from the Florida Department of Revenue. The Florida Department of Revenue compiles the database based on county.

1. Download the files from the Florida website at:  
<https://pointmatch.state.fl.us/General/AddressFiles.aspx/>.
2. Unzip the downloaded files and transfer them to the server.

**Note:** Be sure to FTP your files in binary format.

3. Combine the county files into a single file if you downloaded more than one county. If you downloaded the entire state list, you have approximately 67 files. You must combine all the files into one file.  
Your file is ready for loading.

## Downloading TS-158 Format Files

The Federation of Tax Administrators (FTA) maintains a website with links to all data sources that use the TS-158 format.

1. Download the files from the Florida website at:  
<https://pointmatch.state.fl.us/General/AddressFiles.aspx>.
2. Unzip the downloaded files and transfer them to the Spectrum™ Technology Platform server.
3. State files are often broken up into individual county files. Combine all state and/or county files into a single file.  
Your file is ready for loading.

## Database Options

The following describes the database options presented in the Windows Database Load Utility.

### GeoTAX master files

The GeoTAX/Enterprise Tax Premium Database is a required dataset and is the master file for the Enterprise Tax Module software. The master files identify all geographic components associated with a street address, such as the latitude/longitude, census tract, and block group.

### Point Data files

Point Data products include Master Location Data (MLD), Centrus Points, Centrus NAVTEQ Points, and Centrus TomTom Points. The point data provides point-level geocoding for the most accurate placement of addresses throughout the U.S. The Master Location Data database provides the best available address point location for every mailable and deliverable address in the United States.

### User auxiliary file

This is a user-defined file that the Enterprise Tax Module uses to override results from the master files in street-level matching. If you have data that is more current than that in the master files, you can enter the new data into the auxiliary file and use it for your address matching. The Enterprise Tax Module returns matches made with a code that signifies the answer came from the auxiliary file. You can also return user-defined data from the auxiliary file with the match. The install program creates the file `G1GTAUX` in the specified destination.

### GeoTAX auxiliary file

This file contains new addresses that have not yet been added to the master files. It provides the most up-to-date address data possible. The install program creates the indexed sequential file `G1GTAX2` in the specified destination.

### Landmark auxiliary file

This is a user-defined file that allows you to specify customized address information in your input records. The recommended primary use of this file to match to your

company's non-address locations such as well heads, transmission towers or any other descriptive location. The latitude/longitude that is part of the input needed to build this file allows companies to automatically keep track of any jurisdictional changes that affect these unique locations. Matching to this file requires that the input record information match exactly to the Landmark file contents. This also applies to street records if you choose to enter them in the Landmark file. For more information, refer to the *Enterprise Tax Module Guide*.

### **State-supplied Florida format file**

This is a state-supplied file in Florida-native format which is provided by individual state governments. The Enterprise Tax Module first attempts to match to the state database. If the Enterprise Tax Module cannot find a state match, it attempts a match to the GeoTAX Auxiliary file, if loaded, then to the master files.

### **State-supplied TS-158 format file**

This is a state-supplied file in TS-158 (ANSI Transaction Set No. 158) format which is provided by individual state governments. The Enterprise Tax Module first attempts to match to the state database. If the Enterprise Tax Module cannot find a state match, it attempts a match to the GeoTAX Auxiliary file, if loaded, then to the master files.

### **Boundary file**

Boundary files provide additional data about locations of special tax districts:

- Special Purpose Tax Districts (spd.txb)
- Insurance Premium Tax Districts (ipd.txb)
- Payroll Tax Districts (pay.txb)
- Personal Property Tax Districts (ptd.txb)
- User-defined Boundary file (usr.txb)

### **PB Software tax rate file**

The Pitney Bowes Software Sales and Use Tax Rate file allows you to use the Enterprise Tax Module to provide sales and use tax rates for each of the assigned tax jurisdictions as well as the total rate for the assigned locations. The install program creates the indexed sequential file `GTTAXRT`.

### **Payroll tax correspondence file**

Payroll tax cross-reference file allow you to use third-party software to determine the payroll tax rates. The cross-reference files combine the U.S. Government Federal Information Processing Standards (FIPS) codes with the proprietary geocodes used by tax software from third parties. The Payroll System Tax Code file is a customized file that you build to return the payroll tax codes used by your payroll system. The install program produces database files called `G1GTPTC` and `G1GTPTC.vix`.

### **Taxware<sup>®</sup> cross reference file**

This sales tax cross-reference file enables you to use the Enterprise Tax Module to determine tax jurisdictions for a given address, then use Taxware<sup>®</sup> software to determine the sales tax rates for those jurisdictions.

### **Vertex<sup>®</sup> cross reference file**

This sales tax cross-reference files allows you to use the Enterprise Tax module to determine tax jurisdictions for a given address, then use Vertex<sup>®</sup> software to determine the sales tax rates for those jurisdictions.

### **PB Software Vertex<sup>®</sup> cross reference file**

This is a Vertex<sup>®</sup> cross-reference file supplied by Pitney Bowes. The install program produces a database file `GTMSTR2` in the specified destination.

## Installing the Database Files

1. Select **Start > Programs > Pitney Bowes > Spectrum<sup>™</sup> Technology Platform > Modules > Enterprise Tax Module > Database Load Utility**.

The Database Load Utility window launches.

2. Select the database you want to install.

**Note:** For Point Data, select the **GeoTAX master files** option.

3. Follow the instructions provided by the wizard.

**Note:** When specifying the destination directory:

- All Enterprise Tax Module databases and cross-reference files must be installed in the same directory.
- You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

4. In Management Console, open the Enterprise Tax Module database resource tool and define a database resource that includes the database you just installed. Be sure to update Assign GeoTAX Info and Reverse GeoTAX Info Lookup to use the new database resource.

## Installing GeoEnrichment Module Databases

1. Download your database(s). The database is downloaded as a `.tar.bz2` file.
2. Extract the `.tar.bz2` file.

**Tip:** A tool that supports extracting the `.tar.bz2` and `.tar` formats is "7-Zip". This open-source tool can be downloaded from: <http://www.7-zip.org/download.html>

3. Extract the `.tar` file.
4. Copy the data to any directory. Note the file name and path.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

- After you install the database files, you will need to define the database as a resource. For more information, see "Adding a GeoEnrichment Module Database Resource" in the *GeoEnrichment Guide* on [support.pb.com](http://support.pb.com).

## Installing Global Addressing Module Databases

This procedure describes how to download and install Global Addressing Module databases in the Spectrum™ Product Database (SPD) format from the Pitney Bowes eStore.

### Disk Space

The disk space requirements for extracted and non-extracted SPD bundles are:

- Extracted bundles (all SPD) - 50 GB
- Non-extracted bundles (all SPD) - 20 GB

### Memory

The following table provides information on the Global Address Module memory requirements for each country database.

**Table 1: Global Address Validation Memory Requirements (in Megabytes)**

Country Database Name	Global Address Validation	Global Type Ahead	Both
Argentina (ARG)	700	n/a	n/a
Australia (AUS)	700	n/a	n/a
Austria (AUT)	900	700	1900
Belgium (BEL)	900	700	1900
Brazil (BRA)	700	700	700
China (CHN)	700	n/a	n/a
Czech Republic (CHZ)	700	n/a	n/a



Country Database Name	Global Address Validation	Global Type Ahead	Both
Denmark (DNK)	2100	700	3400
Finland (FIN)	900	700	1900
France (FRA)	2800	700	4100
Germany (DEU)	700	700	1900
Greece (GRC)	700	n/a	n/a
India (IND)	700	n/a	n/a
Ireland (IRL)	900	700	1900
Italy (ITA)	700	700	1900
Japan (JPN)	700	n/a	n/a
Malaysia (MYS)	700	n/a	n/a
Mexico (MEX)	700	n/a	n/a
Netherlands (NLD)	700	n/a	n/a
New Zealand (NZL)	700	n/a	n/a
Norway (NOR)	700	700	1900
Poland (POL)	700	n/a	n/a
Russia (RUS)	700	n/a	n/a
Spain (ESP)	1300	700	1900
Sweden (SWE)	900	n/a	n/a
Switzerland (CHE)	700	700	1900
United Kingdom (GBR)	980	700	1900

To download and install a Global Addressing Module database resource in the Spectrum™ Product Database (SPD) format:

1. Make sure no applications are running.
2. Select and download your licensed SPD files (xxx.spd) from the Pitney Bowes eStore using the link provided in the release announcement or welcome email.
3. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
4. Install the SPD files:
  - a) Place the SPD files in `<SpectrumLocation>/server/app/dataimport`. This is the default location for SPD files. The Spectrum™ Technology Platform server monitors this folder and looks for new files in two-second intervals.  
You can change the location of the data import directory by altering the **platform** property in the `<SpectrumLocation>/server/app/conf/dataimportdirectories.properties` file.
  - b) When the server detects new SPD files, the server automatically extracts the SPD files to `<SpectrumLocation>/server/app/repository/datastorage`.  
You can change the location of the data storage folder by altering the **spectrum.data.manager.storage.directory** property in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file.
  - c) By default, the SPD files are deleted after the files are extracted. However, you can archive SPD files by setting the **spectrum.data.manager.archive.data** property to "true" in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file.
  - d) At this point the data will become available and you can add it as a Spectrum™ database resource in the **Spectrum™ Databases** section of Management Console.
  - e) After you install the database files, use either the Database Resource tool in the Management Console or the Global Addressing Administration Utility database commands to define the database as a resource. For more information on the Administration Utility database commands, see the section "Global Addressing Module Databases" in the *Spectrum™ Technology Administration Guide*.

## Installing Global Geocoding Module Databases

This module supports databases for both US and non-US countries.

## International Geocoding Databases

International geocoding databases contain the data necessary to perform geocoding and reverse geocoding for locations outside the U.S.

**Note:** To install the Global Geocoding Module databases on Windows Server 2008 you need administrator privileges.

**Note:** Do not install geocoding databases on a network drive. Doing so can cause performance problems.

1. Download your licensed SPD files from the Pitney Bowes eStore using the link provided in the release announcement or welcome email.
2. Place the .spd files in:

```
SpectrumLocation/server/app/dataimport
```

The SPD file is automatically extracted to:

```
SpectrumLocation/server/app/repository/datastorage
```

Once the database has been extracted to the `datastorage` folder, it is installed and you can define it as a database resource using Management Console. Find more information about Management Console in the Administration Guide.

You can modify the Spectrum database installation process if needed:

- You can change the location of the data import directory by altering the **platform** property in the `<SpectrumLocation>/server/app/conf/dataimportdirectories.properties` file.
- You can change the location of the data storage folder by altering the **spectrum.data.manager.storage.directory** property in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file. Consider creating a storage folder outside of Spectrum so it will not be deleted when you uninstall Spectrum.
- By default, the SPD files are deleted after the files are extracted or when Spectrum is uninstalled. However, you can archive SPD files by setting the **spectrum.data.manager.archive.data** property to "true" in the Data Manager settings section of the `<SpectrumLocation>/server/app/conf/spectrum-container.properties` file.
- With any change to properties files, you must stop and restart the Spectrum server.

## U.S. Geocoding Databases

The U.S. geocoding databases contain the spatial data necessary to perform address standardization and geocoding. You must install at least one of these databases.

- **TomTom Geocoding**—This database provides street segment data by TomTom, a third-party provider of spatial data, and postal data from the U.S. Postal Service.
- **NAVTEQ Geocoding**—This database provides street segment data by NAVTEQ, a third-party provider of spatial data.

These databases use proprietary files called GSD files. For ZIP Code centroid matching, the file `us.Z9` contains all the centroid info for all states and normally has a `z9` extension.

Each geocoding database has an optional Statewide Intersections Index. The Statewide Intersection Index is designed to enable fast intersection identification on a statewide basis. For example, the Statewide Intersection Index will allow the database to search for "1st and Main St, CO" and return a list of possible matches in Colorado more quickly than searching the entire geocoding database for each instance of the intersection.

**Note:** To install the Global Geocoding Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Download the database from the Pitney Bowes Software eStore using the link provided in the release announcement or welcome email. You can also download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).
3. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
4. Run `DataSets.exe`. The installation wizard guides you through the rest of the process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

5. After you install the database files, use either the Global Geocoding Database Resource tool in the Management Console or the Global Geocoding CLI database commands to define the database as a resource. For more information, see the *Administration Guide*.

## Points Databases (U.S. Only)

Points databases contain data for locating the center of a parcel. These databases provides enhanced geocoding accuracy for internet mapping, property and casualty insurance, telecommunications, utilities, and others.

**Note:** To use a points database, you must also install a streets database. See [U.S. Geocoding Databases](#) on page 91 for the list of available US streets databases.

- **Master Location Data**—This database provides the best available address point location for every mailable and deliverable address in the United States.
- **Centrus Points**—This database contains the data necessary to locate the center of a parcel or building. It does not contain assessor's parcel number (APN) or elevation data.

- **Centrus Elevation**—This database contains the same data as Centrus Points, plus elevation data.
- **Centrus Enhanced Points**—This database contains the same data as Centrus Points, plus APN data.
- **Centrus Premium Points**—This database contains the same data as Centrus Points, plus both APN and elevation data.
- **TomTom Points**—The data in this database is provided by TomTom, a third-party provider of spatial data.
- **NAVTEQ Points**—This database is provided by NAVTEQ, a third-party data provider. It contains data used to locate addresses at the center of the actual building footprint or parcel.

**Note:** To install the Global Geocoding Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the Pitney Bowes web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

3. Run `Setup.exe`. The installation wizard guides you through the rest of the process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

4. After you install the database files, use either the Global Geocoding Database Resource tool in the Management Console or the Global Geocoding CLI database commands to define the database as a resource. For more information, see the *Administration Guide*.

## Installing the Global Sentry Module Database

These databases are required to run Global Sentry in real-time mode:

- ofac.db
- pep.db
- sanctions.db

These files are required to run Global Sentry in batch mode:

- globalsentrydb.addresses-ofac.csv
- globalsentrydb.fullNames-ofac.csv
- globalsentrydb.ids-ofac.csv

- globalsentrydb.names-ofac.csv
- globalsentrydb.addresses-pep.csv
- globalsentrydb.fullNames-pep.csv
- globalsentrydb.ids-pep.csv
- globalsentrydb.names-pep.csv
- globalsentrydb.addresses-sanctions.csv
- globalsentrydb.fullNames-sanctions.csv
- globalsentrydb.ids-sanctions.csv
- globalsentrydb.names-sanctions.csv

In addition, you must install the **Data Normalization Module** and **Advanced Matching Module** databases to use Global Sentry. For instructions, see [Installing Data Normalization Module Databases](#) on page 78 and [Installing the Advanced Matching Module Database](#) on page 77.

Ensure the Global Sentry Database Server is in up and running. In case it is not, use the option in the utility to start it before you begin data loading.

**Note:** You need to perform data loading after every upgrade of Spectrum™ Technology Platform.

1. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Stop Server**.
2. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the Pitney Bowes web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

3. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Global Sentry Module > Global Sentry Module Database Load Utility**.
4. Follow the prompts during the rest of the installation process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

5. Start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.
6. After installing the Global Sentry Module database, you must configure a JDBC connection in the Spectrum™ Technology Platform Management Console. Go to **Start > Settings > Control Panel > Administrative Tools > Services** to verify that the Global Sentry Database is running.
7. Log in to the **Management Console** and configure the driver and connection properties using these steps:
  - a) In a web browser go to this URL:

`http://server.port/managementconsole`

Where *server* is the server name or IP address of your Spectrum™ Technology Platform server and *port* is the HTTP port used by Spectrum™ Technology Platform. By default, the HTTP port is 8080.

- b) Enter your user name and password to access the **Home** page of the **Management Console**.
- c) On the Main Menu, click **Systems > Drivers** to open the **Drivers** page
- d) Click **Add**
- e) Type these JDBC properties in the applicable text boxes:
  - JDBC driver configuration name: HSQLDB
  - JDBC driver class name: org.hsqldb.jdbcDriver
  - Connection string template: jdbc:hsqldb:hsq://\${host}:\${port}/\${instance}
- f) Add this driver file:
 

```
<SpectrumPlatformLocation>/GlobalSentryDatabase/lib/hsqldb.jar
```
- g) To define connection properties, go to **Resources > Data Sources**.
- h) Click **Add**, and define these connection properties:
  - Connection name: Global Sentry
  - Database driver: select the HSQLDB JDBC driver that you created in the previous steps.
- i) Enter these values in the **Connection Properties** dialog box:
  - user: sa
  - password: <there is no password>
  - host: localhost or <your server name>
  - port: 9001
  - instance: globalsentrydb
- j) Click **Test** to verify the connection works.
- k) Click **OK**, then click **Save**

## Installing Location Intelligence Module Databases

1. Place the data on the file system, or install the data into a database.
2. Use Spatial Manager to define Location Intelligence Module database resources (named connections and tables). For more information, see the "Configuring Database Resources" chapter of the *Spectrum™ Technology Platform Administration Guide* on [support.pb.com](http://support.pb.com).

## Installing Universal Addressing Module Databases

This procedure describes how to install databases used by Get Candidate Addresses, Get City State Province, Get Postal Codes, Validate Address, and Validate Address AUS. For instructions on installing databases used by Validate Address Global, see [Installing Validate Address Global Databases](#) on page 96. For instructions on installing databases used by Validate Address Loqate, see [Installing Validate Address Loqate Databases](#) on page 97.

**Note:** To install the Universal Addressing Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Download the database from the Pitney Bowes Software eStore using the link provided in the release announcement or welcome email. You can also download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).
3. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
4. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Universal Addressing Module > Database Load Utility**.
5. Follow the prompts during the rest of the installation process.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

6. If you choose to install Residential Delivery Indicator, an optional database that you license directly from the U.S. Postal Service, you are prompted for the nine-digit RDI table and the eleven-digit RDI table. These are called rts.hs9 and rts.hs11, respectively, and they are provided by the U.S. Postal Service.

## Installing Validate Address Global Databases

This procedure describes how to install the databases used by the Validate Address Global stage. For instructions on installing databases used by other Universal Addressing Module stages, see the *Spectrum™ Technology Platform Administration Guide*.

1. Download the database from the Pitney Bowes Software eStore using the link provided in the release announcement or welcome email. You can also download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).
2. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
3. Unzip the database file to the location you want. The database zip files are:



- VAGlobal-EMEA.zip—Contains the data for Europe, Middle East, and Africa.
- VAGlobal-APAC.zip—Contains the data for Asia-Pacific.
- VAGlobal-Americas.zip—Contains the data for the Americas.

**Note:** You may install databases on a network share, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

4. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the system tray and select **Stop Spectrum™**.
5. Install the unlock code:
  - a) Open the following file in a text editor:  
`<SpectrumLocation>\server\modules\addressglobal\conf\unlockcodes.txt`
  - b) Enter your unlock codes, one per line.
  - c) Save and close the file.
6. Start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the system tray and select **Start Spectrum™**.

## Installing Validate Address Loqate Databases

This procedure describes how to install the databases used by the Validate Address Loqate stage. For instructions on installing databases used by other Universal Addressing Module stages, see the *Spectrum™ Technology Platform Administration Guide*.

1. Download the database from the Pitney Bowes Software eStore using the link provided in the release announcement or welcome email. You can also download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).
2. The database is downloaded as a zip file. Unzip the database before proceeding with the installation.
3. Unzip the database file(s) to the location you want. If you are installing data from multiple zip files or discs, be sure to unzip them all to the same location. The database zip files are:
  - LQ0/DB\_Setup—Contains general database setup files.

**Note:** Regardless of which set of data you use, the files in LQ0 must be installed.

- LQ1/APAC\_AFR\_ME-I—Contains the data for Asia-Pacific, Africa, and Middle East.
- LQ2/Americas-I—Contains the data for the Carriibbean, Central America, and South America.
- LQ3/Europe-I—Contains the data for Eastern and parts of Western Europe.
- LQ4/Americas-II—Contains the data for parts of North America.
- LQ5/Europe-II—Contains the data for parts of Western Europe.
- LQ6/Americas-III—Contains the data for parts of North America.
- LQ7/APAC\_AFR\_ME-II—Contains the data for parts of Asia-Pacific, Africa, and Middle East.

- LQ8/Europe-III—Contains the data for parts of Western Europe.

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

4. From the location where you extracted the database files, right-click **install.bat** and select **Run as administrator**. This will launch the Loqate Installer.
5. Follow the prompts during the rest of the installation process.

## Installing Universal Name Module Databases

The Universal Name Module provides a load utility to install databases. The database files that you load depend on the databases you have licensed.

**Note:** To install the Universal Name Module databases on Windows Server 2008 you need administrator privileges.

1. Make sure no applications are running.
2. Stop Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Stop Server**.
3. Insert the database DVD or download the database from the technical support web site, [www.g1.com/support](http://www.g1.com/support).

**Note:** If you download the database from the web site, it will be downloaded as a zip file. Unzip the database before proceeding with the installation.

4. Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Universal Name and Advanced Matching Modules > Database Load Utility**.
5. Follow the prompts to complete the installation process. The database files you can install are:

- Arabic Plus Pack: `g1-cdq-cjki-arabic-<date>.jar`
- Asian Plus Pack - Chinese: `g1-cdq-cjki-chinese-<date>.jar`
- Asian Plus Pack - Japanese: `g1-cdq-cjki-japanese-<date>.jar`
- Asian Plus Pack - Korean: `g1-cdq-cjki-korean-<date>.jar`
- Core Names Database: `g1-cdq-nomino-base-<date>.jar`

**Note:** You may install databases on a mapped drive, but performance will be affected since you will be accessing them on a network rather than accessing them locally.

6. To load the complete Core Names Database, you must also install Open Parser and Table Lookup data from the Data Normalization Module Database Load Utility.

- a) Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Data Normalization Module > Database Load Utility > Open Parser**.
  - b) Follow the prompts to complete the installation process. The database file you need to install is:
    - cdq-OpenParser-EnhancedNames.tba
  - c) Select **Start > Programs > Pitney Bowes > Spectrum™ Technology Platform > Modules > Data Normalization Module > Database Load Utility > Table Lookup**.
  - d) Follow the prompts to complete the installation process. The database file you need to install is:
    - cdq-TableLookup-EnhancedGenderCodes.tba
7. Open the file `<SpectrumDirectory>\server\bin\wrapper\wrapper.conf` in a text editor.
  8. Increase the Java settings for initial heap size (`wrapper.java.initmemory`) and maximum heap size (`wrapper.java.maxmemory`) to reflect the total amount of memory required for the Arabic Plus Pack and Asian Plus Pack.
    - Arabic Plus Pack: 5.5 GB
    - Asian Plus Pack - Chinese: 32 MB
    - Asian Plus Pack - Japanese: 1.6 GB
    - Asian Plus Pack - Korean: 8 MB
    - Core Names: 1.1 GB
  9. Save and close `wrapper.conf`.
  10. Start Spectrum™ Technology Platform. To do this, right-click the Spectrum™ Technology Platform icon in the Windows task bar and select **Start Server**.

## Using the Database Silent Installer

The silent install process allows you to pre-configure the database installation process so that it runs without user intervention. Instead of responding to prompts from the installation process for information such as the installation location, you specify these responses in a properties file that the installer uses instead of user prompts.

## Using the Loqate Database Silent Installer

1. In the Spectrum™ Technology Platform server installer (not the database installer), browse to the `SilentInstaller` folder.

2. Using a text editor, open the `uam_loqate.installer.properties` file.
3. Edit the properties file as necessary to specify the installation settings you want to use. See the comments in the properties file for additional information.
4. To run the installer in silent mode, place the properties file in any directory except the location where you are going to install the Loqate data and give the absolute path to the property in the command prompt, as follows:

```
install.bat %PathOfPropertyFile%\uam_loqate.installer.properties
```

# 6 - Client Tools

## In this section

---

Installing the Client Tools	102
Installing Enterprise Designer with a Silent Installer	103
Upgrading Enterprise Designer	104
Removing Enterprise Designer	105

## Installing the Client Tools

The Spectrum™ Technology Platform client tools are applications that you use to administer your server and design and run dataflows and process flows. You must install your Spectrum™ Technology Platform server before installing the client tools.

Before installing, be sure to read the release notes. The release notes contains important compatibility information as well as release-specific installation notes.

This procedure describes how to install the following client tools:

- **Enterprise Designer**— Use Enterprise Designer to create, modify, and run dataflows.
- **Job Executor**—Job Executor is a command line tool that allows you to run a job from a command line or script. The job must have been previously created and saved on Spectrum™ Technology Platform using Enterprise Designer.
- **Process Flow Executor**—Process Flow Executor is a command line tool that allows the execution of a process flow from a command line or script. The process flow must have been previously created and saved on Spectrum™ Technology Platform using Enterprise Designer.
- **Administration Utility**—The Administration Utility provides command line access to several administrative functions. You can use it in a script, allowing you to automate certain administrative tasks. You can also use it interactively.

**Note:** As of Spectrum version 11.0, Management Console is a web-based tool rather than installable client as it was in previous releases.

To install the client tools:

1. Open a web browser and go to the Spectrum™ Technology Platform Welcome Page at:

`http://<servername>:<port>`

For example, if you installed Spectrum™ Technology Platform on a computer named "myspectrumplatform" and it is using the default HTTP port 8080, you would go to:

`http://myspectrumplatform:8080`

2. Click **Platform Client Tools**.
3. Download the client tool you want to install.

## Installing Enterprise Designer with a Silent Installer

The silent install process installs Enterprise Designer without user intervention. Instead of prompting the user for information such as the installation location, the installer uses pre-configured selections that you specify.

To use the silent installer you must first create an installer properties file by running the client installer and responding to the prompts. The resulting properties file can then be used to silently install Enterprise Designer on other computers.

1. Open a web browser and go to the Spectrum™ Technology Platform Welcome Page at:

`http://<servername>:<port>`

For example, if you installed Spectrum™ Technology Platform on a computer named "myspectrumplatform" and it is using the default HTTP port 8080, you would go to:

`http://myspectrumplatform:8080`

2. Click **Platform Client Tools**.
3. Click **Download Installer**.
4. Choose to save the file to a location on your computer.

**Note:** Save the installer on a Windows computer that does not already have Enterprise Designer installed. You will need to run the installer in order to specify the options you want to use in the silent install process.

5. Open a Windows command prompt.
6. In the command prompt, change directories to the directory where you saved the installer.
7. Execute the following command:

```
Setup.exe -r installer.properties
```

8. Respond to the installer prompts by selecting the options that you want to use when the installer runs silently.

For example, if you want the silent installer to install Enterprise Designer to `C:\Spectrum\EnterpriseDesigner`, specify `C:\Spectrum\EnterpriseDesigner` when prompted for an installation folder.

When the installer finishes running, a properties file named `installer.properties` is created in the same folder as the `Setup.exe` file.

9. Open the file `installer.properties` in a text editor.

10. Add the following on line 8 of the file:

```
INSTALLER_UI=silent
```

**Note:** This is case sensitive to be sure to enter it exactly as shown above.

11. Save and close the properties file.

You have now configured a properties file that will enable you to install Enterprise Designer silently.

12. To install Enterprise Designer silently, place `installer.properties` and `Setup.exe` in the same folder on the computer where you want to install Enterprise Designer and run `Setup.exe`. When the installer executes it will detect `installer.properties` and automatically run in silent mode.

Alternatively, you can place `installer.properties` in different directory and give the absolute path to the property in the command prompt using the `-f` argument, as follows:

```
Setup.exe -f PathOfPropertyFile\installer.properties
```

## Upgrading Enterprise Designer

### *Upgrading from 12.0 or 11.0 SP1*

If you are upgrading to Spectrum™ Technology Platform 12.0 SP1 from 12.0 or 11.0 SP1, you do not need to upgrade Enterprise Designer. However, you should delete this file before logging into 12.0 SP1:

```
C:\Users\UserName\AppData\Roaming\Pitney Bowes\Enterprise  
Designer\Settings.xml
```

### *Upgrading from a version prior to 11.0*

If you are upgrading to Spectrum™ Technology Platform 12.0 SP1 from a version prior to 11.0 SP1, you must upgrade Enterprise Designer due to security changes.

**Important:** Once you upgrade your server to 12.0 SP1, you will not be able to log in to Enterprise Designer until you upgrade it.

To upgrade Enterprise Designer:

1. Uninstall the existing client tools by going to **Start > All Programs > Pitney Bowes > Client Tools > Setup**.



2. Make sure that you have .NET 4.6 installed on the client machine. This is a newer version of .NET than was required in previous releases. Note that Windows 10 comes with this version of .NET installed by default.
3. Download the client tools installer from the Spectrum™ Technology Platform welcome page, <http://SpectrumServer:Port>. The default port is 8080.
4. Run the installer.

## Removing Enterprise Designer

1. Back up any files you may need in the future.
2. Use the Windows Add/Remove Programs control panel to uninstall Enterprise Designer.

# 7 - Client API

## In this section

---

Installing the Client API	107
Removing the Client API	107

## Installing the Client API

The Client API is used to integrate Spectrum™ Technology Platform functionality into your applications. If you will be creating your own program to call Spectrum™ Technology Platform, you need to install the Spectrum™ Technology Platform Client API on the system where you will be developing your application. The Client API allows access to Spectrum™ Technology Platform through several programming languages, including Java, C++, and web services.

1. Open the folder where you have downloaded the Spectrum™ Technology Platform Client API installer.
2. Double-click the file `sdkinst.exe`.
3. The installer guides you through the installation process.

## Removing the Client API

Use the Windows Add/Remove Programs control panel to uninstall the Spectrum™ Technology Platform Client API.

# 8 - SAP, Siebel, SugarCRM, and Microsoft Dynamics

## In this section

---

Configuring SAP	109
Configuring Siebel	117
Configuring SugarCRM	164
Configuring Microsoft Dynamics CRM	168

# Configuring SAP

## Integrating with SAP

To integrate Spectrum™ Technology Platform with SAP, you need to install supporting databases and dataflows on the Spectrum™ Technology Platform server, and then configure your SAP system to communicate with Spectrum™ Technology Platform. Once you do this, users of SAP will have access to address validation and geocoding functionality from within SAP.

1. On the Spectrum™ Technology Platform server, install the databases required to perform address validation, geocoding, and tax jurisdiction assignment and define database resources for each database.

You must give the database resources the following names.

Database	Required Name for Database Resource
Enterprise Geocoding Module - Canada Database	IGEO_CAN
Enterprise Geocoding Module - U.S. Database	EGM_US
Enterprise Tax Module Database	ETM
Universal Addressing Module - Canada Database	Canada
Universal Addressing Module - Loqate Database	Loqate
Universal Addressing Module - U.S. Database	UAM_US

2. When you install the SAP Module, several dataflow files are automatically installed. Other dataflow files must be manually copied into Spectrum™ Technology Platform.
  - a) If you are adding the Address Now Module, Enterprise Tax Module, or Universal Addressing Module to an existing installation, open Spectrum™ Technology Platform Enterprise Designer, select **View > Server Explorer**, and delete this dataflow:  
SAPValidateAddressWithCandidates.
  - b) Go to: *SpectrumFolder\server\modules\dataflows\sap*.
  - c) Review the following table then copy the applicable dataflow files to:

*SpectrumFolder\server\app\import*

If you are installing this set of modules Copy these dataflow files to the import folder

Address Now Module	SAPValidateAddressWithCandidates.ANOW.df
Address Now Module Universal Addressing Module	SAPValidateAddressWithCandidates.ANOW.df SAPValidateAddressWithCandidates.UAM.df
Address Now Module Enterprise Geocoding Module	SAPValidateAddressWithCandidates.ANOW_EGM.df
Address Now Module Enterprise Geocoding Module Universal Addressing Module	SAPValidateAddressWithCandidates.UAM_ANOW_EGM.df
Address Now Module Enterprise Tax Module Universal Addressing Module	SAPAssignGeoTAXInfo.df SAPBatchAssignGeoTAXInfo.df  SAPValidateAddressAndAssignGeoTAXInfo.df SAPValidateAddressWithCandidates.UAM_ANOW_ETM.df
Address Now Module Enterprise Geocoding Module Enterprise Tax Module Universal Addressing Module	SAPValidateAddressWithCandidates.UAM_ANOW_ETM_EGM.df
Universal Addressing Module without Loqate	SAPValidateAddressWithCandidate_UAM.df
Universal Addressing Module without Loqate Enterprise Tax Module	SAPAssignGeoTAXInfo.df SAPBatchAssignGeoTAXInfo.df  SAPValidateAddressAndAssignGeoTAXInfo.df SAPValidateAddressWithCandidates.UAM_ETM.df

If you are installing this set of modules Copy these dataflow files to the import folder

---

Universal Addressing Module with Loqate	ValidateAddressWithCandidates_UAM_Loqate.df
---	---

---

Universal Addressing Module with Loqate Enterprise Geocoding Module	ValidateAddressWithCandidates_UAM_Loqate_EGM.df
--	---

---

Universal Addressing Module with Loqate Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_ETM.df
--	---

---

Universal Addressing Module with Loqate Enterprise Geocoding Module Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_EGM_ETM.df
---	---

---

Universal Addressing Module, Loqate only	ValidateAddressWithCandidates_Loqate.df
--	---

---

Universal Addressing Module, Loqate only Enterprise Geocoding Module	ValidateAddressWithCandidates_Loqate_EGM.df
---	---

---

Enterprise Geocoding Module	GeocodeUSAddressWithCandidates.df ValidateAddressWithCandidates_EGM.df
-----------------------------	---

---

Enterprise Tax Module	ValidateAssignGeoTAXInfo.df ValidateAddressWithCandidates_ETM.df SAPBatchAssignGeoTAXInfo.df
-----------------------	--

---

**Note:** If errors occur in Management Console or Enterprise Designer, delete the contents of <WindowsTemporaryDirectory>\glAssemblies, where <WindowsTemporaryDirectory> is one of the following: %TMP%, %TEMP%, %USERPROFILE%, or the Windows directory. Typically, C:\Documents and

Settings\<>USERNAME>\Local Settings\Temp\g1Assemblies. After you delete the contents of this folder log in again.


### 3. Import .SAR files.

A .SAR file is a file that contains a third-party add-on package for SAP, such as the Spectrum™ Technology Platform SAP Module. The .SAR file is located on the Spectrum™ Technology Platform installer in the `SAP Objects` folder. For information on importing .SAR files into SAP applications, see your SAP Basis administrator.

### 4. Activate the business configuration (BC) sets. The activation options and sequence differs for ECC and CRM installations.

#### a) Activate BC sets for ECC and S/4 HANA installations

1. Log-on to the client where the settings for the Spectrum™ Technology Platform SAP Module is to be configured.
2. Enter the transaction code `SCPR20`. This activates BC sets and places the default entries on the Spectrum™ Technology Platform customizing tables.
3. In the **BC Set** field, enter `/HSGRP1/BCSET_BC_BAS_PV`.
4. Activate it with the options **Overwrite All Data** and **Default Mode**.



### 5. Select and activate the remaining BC sets with the activation options set to **Overwrite All Data** and **Expert Mode**

**Note:** Activate these BC sets in the order listed.

```
/HSGRP1/BCSET_BC_BAS_GTX
/HSGRP1/MERGE_SETTINGS
/HSGRP1/BCSET_BUPA_CUSTOM
/HSGRP1/BCSET_BC_BAS_DES
/HSGRP1/BCSET_DQC_CUSTOM
```



b) **Activate BC sets for CRM installations**

1. Log-on to the client where the settings for the Spectrum™ Technology Platform SAP Module is to be configured.
2. Enter the transaction code `SCPR20`. This activates BC sets and places the default entries on the Spectrum™ Technology Platform customizing tables.
3. In the **BC Set** field, enter `9. /HSGRP1/BCSET_BC_BAS_DES`.
4. Activate it with the options **Overwrite All Data** and **Default Mode**.

5. Select and activate the remaining BC sets with the activation options set to **Overwrite All Data** and **Expert Mode**

**Note:** Activate these BC sets in the order listed.

`/HSGRP1/BCSET_BC_BAS_PV`  
`/HSGRP1/BCSET_BC_BAS_GTX`  
`/HSGRP1/ICWC_SETTING`  
`/HSGRP1/MERGE_SETTINGS`

5. Set up the RFC destination.
  - a) Enter transaction code `SM59`.
  - b) Click **Create**.
  - c) In the **RFC Destination** field, enter a name of your choice.
  - d) In the **Connection Type** field, enter `G` (HTTP connection to external server).
  - e) In the **Description 1** field, enter a meaningful description.
  - f) Press the Enter key.
  - g) Click the **Technical Settings** tab.
  - h) In the **Target Host** field, enter the computer name or IP Address of the Spectrum™ Technology Platform server.
  - i) In the **Service No** field enter `8080`.

- j) Click the **Special Options** tab.
- k) Select **No Timeout**.
- l) Select **HTTP 1.1**.
- m) After you save, click **Connection Test**.

**Note:** If there is a pop-up window, check the **Accept All Further Cookies** box and select YES.

- n) When the test is successful, go to the **Response Body** tab to view the Spectrum™ Technology Platform page.
6. Set up the Spectrum™ Technology Platform Logging Object
    - a) Enter transaction code `SLG0`.
    - b) Click **New Entries**.
    - c) In the **Object** column, enter `/HSGRP1/DQC`.
    - d) In the **Object text** column, enter `DQC Logging`.
    - e) Save the change.
  7. Configure the BuildGlobalAddress web service in the SAP Visual Admin:
    - a) Go to `<drive>:/usr./sap/<system id>/DVEBMGS01/j2ee/admin` and click `go.bat` and enter `J2EE_ADMIN` password.
    - b) Go to **Cluster > Server > Services > JCo RFC Provider** and select the **Bundles** tab.
    - c) Enter all of the information needed by the application and click **Set** to save the changes.
    - d) Go to **Cluster > Server > Services > Web Services Security**.
    - e) Create a proxy in **Web Services Client > sap.com > Dynamic WSProxies** with the name `PBBIWebServiceConnectorBGA`.
    - f) For the URL, enter:
 

```
http://<spectrumservername>:<port>/soap/BuildGlobalAddress?wsdl
```

For example,

```
http://MySpectrumServer:8080/soap/BuildGlobalAddress?wsdl
```
    - g) Restart the application server.
  8. If you will be using French address validation, you must install the Data Normalization Module table `cdq-TableLookup-SAP.tba` on the Spectrum™ Technology Platform server. For more information, see the *Spectrum™ Technology Platform Installation Guide*.
  9. To configure DPV and RDI options, open T-code `/hsgrp1/options`, and specify **Y** (to enable) or **N** (to disable), as needed.
    - **PVPO:** For PO Box address validation
    - **PVST:** For street address validation
    - **PVQU:** For batch address validation

## Installing Support Files for Read from SAP

The Read from SAP stage reads data from an SAP database as input to a Spectrum™ Technology Platform dataflow. In order for the Read from SAP stage to access data in your SAP system you must make the following changes on your SAP system:

- Install the SAP Java Connector
- Install the SAP Transport Requests that support Read from SAP

**Note:** You will not be able to use the Read from SAP stage until you perform these steps.

1. Install the SAP Java Connector (SAP JCo).
  - a) Go to [service.sap.com/connectors](https://service.sap.com/connectors) and log in with your SAP Marketplace credentials.
  - b) Go to **SAP JCo Connector > Tools & Services**.
  - c) Download SAP JCo to your system.
  - d) Unzip the SAP JCo zip file to a temporary location.
  - e) Stop the Spectrum™ Technology Platform server.
  - f) Copy the .jar file to the following folder on the Spectrum™ Technology Platform server:
 

```
SpectrumFolder\server\app\lib
```
  - g) Copy the .dll file to the following folder on the Spectrum™ Technology Platform server:
 

```
SpectrumFolder\server\bin\wrapper
```
  - h) Start the Spectrum™ Technology Platform server.
2. Install the SAP Transport Requests that support Read from SAP.

**Note:** The following steps should be performed by your SAP Basis administrator.

- a) In the Spectrum™ Technology Platform installer, go to the folder AP Data Integration Objects\Enterprise System Connectors.
- b) Deploy the SAP Transport Requests contained in this folder. See your SAP documentation for instructions on deploying SAP Transport Requests.

## Compatibility Matrix

These tables give a list of SAP add-on versions and system kernel levels that are compatible with the various releases of Spectrum™ Technology Platform for installation and upgrade of ECC 6.0 and CRM 7.0.

**Table 2: Compatibility Matrix for New Deployment**

Spectrum Release	SAP Add-on Version	SAP System Kernel Level
9.x	9.x	720 and above
10.x	10.x	741 and above
11.x	11.x	741 and above
12.x	12.x	741 and above

**Table 3: Compatibility Matrix for Upgrade**

Spectrum Release	SAP Add-on Version	SAP System Kernel Level
9.x	Any to 9.3	720 and above
10.x	Any to 10.x	741 and above
11.x	Any to 11.x	741 and above
12.x	12.x	741 and above

This table gives the compatibility matrix for new deployment of SAP S/4 HANA 1610 for Spectrum™ Technology Platform 12.x.

Spectrum Release	SAP S/4 HANA 1610 Add-on Version	SAP S/4 HANA 1610 System Kernel Level
<b>New deployment</b>		
12.1	12.1	751 and above

**Note:** It is recommended that you contact the Pitney Bowes representative or coordinator assigned to you before starting the process.

# Configuring Siebel

## Integrating with Siebel Data Quality

To integrate Spectrum™ Technology Platform with Siebel Data Quality, you need to install supporting databases and dataflows on the Spectrum™ Technology Platform server, and then configure your Siebel system to communicate with Spectrum™ Technology Platform. Once you do this, users of Siebel Data Quality will have access to address validation and geocoding functionality from within Siebel Data Quality.

1. On the Spectrum™ Technology Platform server, install the databases required to perform address validation, geocoding, and tax jurisdiction assignment and define database resources for each database.

You must give the database resources the following names.

Database	Required Name for Database Resource
Enterprise Geocoding Module - Canada Database	IGEO_CAN
Enterprise Geocoding Module - U.S. Database	EGM_US
Enterprise Tax Module Database	ETM
Universal Addressing Module - Canada Database	Canada
Universal Addressing Module - Loqate Database	Loqate
Universal Addressing Module - U.S. Database	UAM_US

2. When you install the Siebel module, several dataflow files are automatically installed. Other dataflow files must be manually copied into the Spectrum™ Technology Platform server.
  - a) Browse to one of the following folders on your Spectrum™ Technology Platform server:
    - For Siebel Business Applications, go to:  
<SpectrumPlatformLocation>\server\modules\dataflows\siebel\sea
    - For Siebel Industry Applications, go to:  
<SpectrumPlatformLocation>\server\modules\dataflows\siebel\sia

- b) Review the following table then copy the applicable dataflow files to:

*SpectrumLocation\server\app\import*

**Table 4: Dataflow Files To Import**

If you are installing this set of modules Copy these dataflow files to the import folder

Address Now Module only	SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.ADN.df
Address Now Module Universal Addressing Module	SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.UAM_ADN.df
Address Now Module Enterprise Geocoding Module	GeocodeUSAddressWithCandidates.df SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.EGM_ADN.df
Address Now Module Enterprise Geocoding Module Universal Addressing Module	GeocodeUSAddressWithCandidates.df SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.UAM_EGM_ADN.df
Universal Addressing Module only	ValidateAddressWithCandidates_UAM.df
Universal Addressing Module Enterprise Geocoding Module	GeocodeUSAddressWithCandidates.df ValidateAddressWithCandidates_UAM_EGM.df
Universal Addressing Module Enterprise Tax Module	GeocodeUSAddressWithCandidates.df ValidateAssignGeoTAXInfo.df ValidateAddressWithCandidates_UAM_ETM.df
Universal Address Module with Loqate	ValidateAddressWithCandidates_UAM_Loqate.df

If you are installing this set of modules Copy these dataflow files to the import folder

Universal Addressing Module with Loqate Enterprise Geocoding Module	ValidateAddressWithCandidates_Loqate_EGM.df
Universal Addressing Module, Loqate only Enterprise Geocoding Module	ValidateAddressWithCandidates_Loqate_EGM.df
Universal Addressing Module with Loqate Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_ETM.df
Universal Addressing Module with Loqate Enterprise Geocoding Module Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_EGM_ETM.df
Universal Addressing Module, Loqate only	ValidateAddressWithCandidates_Loqate.df
Enterprise Geocoding Module	ValidateAddressWithCandidates_EGM.df
Enterprise Tax Module	ValidateAssignGeoTAXInfo.df
Global Addressing Module	SiebelGlobalTypeAhead.df

**Note:** If errors occur in Management Console or Enterprise Designer, delete the client cache. To delete the client cache, go to **Tools > Options** in Management Console or Enterprise Designer, click the **Advanced** tab, then click **Clear Cache**. After you clear the cache, restart Management Console or Enterprise Designer.

3. Optional: If you are using the Enterprise Geocoding Module, configure the geocoding dataflow to use the geocoding database resource name you have configured on your system:
  - a) In Enterprise Designer, open the dataflow GeocodeUSAddressWithCandidates.

- b) In each dataflow, open the Geocode US Address stage.
- c) In the **Database** field, select the name of the geocoding database as defined in the Management Console. The default name is KGDDatasource but if the geocoding database has a different name on your system, select the appropriate name.

**Note:** For more information about database resources, see the *Spectrum™ Technology Platform Administration Guide*.

- d) Save and close each dataflow.
4. Copy Siebel objects to your system:
- a) Browse to the location where you downloaded the Spectrum™ Technology Platform installer.
  - b) Browse to the appropriate folder for your version of Siebel as shown in the following table.

Siebel Version	Folder
Siebel Business Applications 8.0 SDQ	Siebel Objects\8.0\Business\SDQ
Siebel Business Applications 8.1.1 SDQ	Siebel Objects\8.1.1\Business\SDQ
Siebel Industry Applications 8.0 SDQ	Siebel Objects\8.0\Industry\SDQ
Siebel Industry Applications 8.1.1 SDQ	Siebel Objects\8.1.1\Industry\SDQ

- c) Copy the contents of the folder to a temporary directory.

**Note:** This temporary folder will be referred to as <Spectrum Package> in the following steps.

5. Create objects and allow object locking:
- a) Log in to Siebel Tools as the user SADMIN. In the **Connect to** field select **Server**.
  - b) In the Object Explorer, click **Project**.
  - c) Create three new records using the following values in the **Name** column. To create a new record, right-click in the Projects area and select **New Record**.
    - Group 1 Data Quality
    - Group 1 EAI Testing
    - Group 1 Workflow
  - d) Open the file <Spectrum Package>\tools\CDQP\_Queries.txt.
  - e) Copy and paste the query contents to the Project list of your Object Manager. Cross-check the query result with the table below and perform the action suggested. To toggle object locking, go to Object Explorer and browse to the Project object. From the Project area, right-click and select the project, and select **Toggle Object Locking**.



**Table 5: Queries for Siebel SDQ**

Siebel Business Applications	Siebel Industry Applications	Project	Action
	X	Account	Toggle Object Locking
X		Account (SCW)	Toggle Object Locking
X	X	Account (SSE)	Toggle Object Locking
X	X	Contact	Toggle Object Locking
		Contact (SSE)	Toggle Object Locking
		CUT Account	Toggle Object Locking
		CUT Siebel Communications	Toggle Object Locking
		CUT Usage	Toggle Object Locking
		DNB Data	Toggle Object Locking
		DeDuplication	Toggle Object Locking
		eAutomotive	Toggle Object Locking
X	X	Employee	Toggle Object Locking
		FINS Contract	Toggle Object Locking
		FINS Contract Info	Toggle Object Locking
		FINS Deal Commercial	Toggle Object Locking
		FINS Financial Services	Toggle Object Locking
		FINS Opportunity	Toggle Object Locking
X	X	Group 1 Data Quality	Create and Toggle Object Locking

Siebel Business Applications	Siebel Industry Applications	Project	Action
X	X	Group 1 EAI Testing	Create and Toggle Object Locking
X	X	Group 1 Workflow	Create and Toggle Object Locking
		List Mgmt (Import)	Toggle Object Locking
X	X	List Mgmt (UI)	Toggle Object Locking
		Mvg	Toggle Object Locking
		Oppty	Toggle Object Locking
		Oppty (SSE)	Toggle Object Locking
X		Personal Contact	Toggle Object Locking
X	X	Picklist	Toggle Object Locking
		Server Component Requests	Toggle Object Locking
		Siebel Sales Enterprise	Toggle Object Locking
		Siebel Universal Agent	Toggle Object Locking
	X	VERT CUT Address	Toggle Object Locking
		VERT Cut Common	Toggle Object Locking

6. Check out the Siebel Projects:

- a) Log in to Siebel Tools as the user SADMIN. In the **Connect to** field select **Local**.
- b) Select **Tools > Check Out**.
- c) Select the projects indicated in the following table and click **Checkout**.

**Table 6: Siebel Projects for SDQ**

Siebel Business Applications	Siebel Industry Applications	Project
	X	Account
X	X	Account (SCW)
X	X	Account (SSE)
X	X	Contact
		Contact (SSE)
		CUT Account
		CUT Siebel Communications
		CUT Usage
		DNB Data
		DeDuplication
		eAutomotive
X	X	Employee
		FINS Contract
		FINS Contract Info
		FINS Deal Commercial
		FINS Financial Services
		FINS Opportunity
		Group 1 Data Quality
X	X	Group 1 EAI Testing

Siebel Business Applications	Siebel Industry Applications	Project
X	X	Group 1 Workflow
		List Mgmt (Import)
X	X	List Mgmt (UI)
		Mvg
		Oppty
		Oppty (SSE)
X		Personal Contact
X	X	Picklist
		Server Component Requests
X		Siebel Sales Enterprise
		Siebel Universal Agent
	X	VERT CUT Address
		VERT Cut Common

7. Import the Spectrum™ Technology Platform Siebel Objects.
  - a) Select **Tools > Import from Archive**.
  - b) Browse to the Spectrum™ Technology Platform installation package. In the *Siebel Objects* folder, browse to the subfolder for your version of Siebel and select the SIF files.
  - c) Select **Merge the object definition in the repository** and click **Next**.
8. Check in all locked projects:
  - a) Select **Tools > Check In**.
  - b) Select all the Projects to check in and click **Check in**.
9. (Open UI Only) Import the Spectrum™ Technology Platform Siebel Objects for Open UI:
  - a) Select **Tools > Import from Archive**.

- b) Browse to the Spectrum™ Technology Platform installation package. In the Siebel Objects folder, browse to the OPEN\_UI subfolder for your version of Siebel and select the SIF files.
  - c) Select **Merge the object definition in the repository** and click **Next**.
10. Compile all Projects:
- a) Select **Tools > Compile Projects**.
  - b) Click **All Projects**.
  - c) In the **Siebel Repository File** field, enter the path of your Siebel Web Client SRF file.
  - d) Click **Compile**.
11. Deploy the Siebel objects in the client:
- Note:** Keep a backup of the old SRF in case old binaries need to be re-implemented.
- a) Copy the generated SRF to your web client objects folder.  
For example, on Windows the web client object folder may be C:\Program Files\Siebel\8.0\web client\OBJECTS\ENU. On Unix or Linux the folder may be /disk2/sia78/webclient/OBJECTS/enu/.
  - b) Copy the contents of <Spectrum Package>\dll to your BIN folder.
  - c) Copy the contents of <Spectrum Package>\cfg to your BIN/ENU folder.
12. Deploy the Siebel objects to the server:
- a) Stop the Siebel server.
  - b) Copy the generated SRF file to your web client objects folder.  
For example, the folder for Siebel Business on Windows may be C:\sea80\siebsrvr\OBJECTS\ENU. On Unix or Linux the folder may be /disk2/sea78/siebsrvr/OBJECTS/enu/.
  - c) Copy the libraries to your server.
    - For Windows, copy the contents of <Spectrum Package>\lib\win to your BIN folder.
    - For Unix or Linux, copy the contents of <Spectrum Package>/lib/sol to your LIB folder.
  - d) Copy the contents of <Spectrum Package>\cfg to your BIN\ENU folder.
  - e) Start the Siebel server.
13. Install the options file.
- a) Click **Site Map > Administration - Data > LOV Explorer**.
  - b) Click **New**.
  - c) In the **Type** column, enter FILE\_PATH.
  - d) Click **Query**.
  - e) In the **Type** column, enter FILE\_PATH.
  - f) Browse to the **Values** folder.

- g) In the **Display Value** column, enter the absolute path to the folder where you want to keep the options file. You can specify any folder you want.
  - h) Browse to the Spectrum™ Technology Platform installation package.
  - i) In the `Siebel Objects` folder, browse to the `cfg` subfolder for your version of Siebel and select the `Group1Connector.opt` file.
  - j) Copy this file to the folder you specified for `FILE_PATH`.
14. Activate the Spectrum™ Technology Platform workflows in the Siebel web client:
- a) Log in to the Siebel application, connecting to the server data source.
  - b) Select **Site Map > Administration - Business Process > Workflow Deployment**.
  - c) Query for all the GROUP 1\* workflows.
  - d) Click **Activate** for each workflow.
  - e) Query for all the Promote\* workflows.
  - f) Click **Activate** for the ff workflows **Promote Prospect (Single)** and **Promote Prospect (Many)**.
15. Verify the installation:
- a) Log in to Siebel Application.
  - b) All applets should load properly without error.
16. Configure the Siebel instance configuration parameters:
- a) Select **Site Map > Administration - Server Configuration > Enterprises**.
  - b) Verify/Change the ff Parameters:
    - Data Cleansing Type—G1Cleansing
    - DeDuplication Data Type—G1DataMatching
  - c) Click **Component Definitions** and select the ff components. For each component, verify parameters and values.

**Table 7: Siebel Business**

Component Definitions	Parameter	Value/Value on Restart
*Data Quality Manager *Sales Object Manager (ENU) *List Import Service Manager	Data Cleansing Type	G1Cleansing
	Data Cleansing Enable Flag	True
	DeDuplication Data Type	G1DataMatching
	DeDuplication Enable Flag	True

**Table 8: Siebel Industry**

Component Definitions	Parameter	Value/Value on Restart
*Data Quality Manager	Data Cleansing Type	G1Cleansing
*eAutomotive Object Manager (ENU) *List Import Service Manager	Data Cleansing Enable Flag	True
	DeDuplication Data Type	G1DataMatching
	DeDuplication Enable Flag	True

- d) Select **Site Map > Server Configuration > Servers**. Repeat steps b through c for server configuration parameters.
- e) Select **Site Map > User Profile Preferences > Data Quality**. Change the following settings:

Parameter	Value
Enable DeDuplication	Yes
Enable Data Cleansing	Yes

- f) Browse to <Siebel Installation>\bin\ENU and open the appropriate file:
- Siebel Business: siebel.cfg and uagent.cfg
  - Siebel Industry: auto.cfg
- g) Under the area [DataCleansing] change the ff Parameters:

```
Enable = TRUE
Type = G1Cleansing
```

- h) Under the area [DeDuplication] change the ff Parameters:

```
Enable = TRUE
Type = G1DataMatching
```

- i) Select **Site Map > Administration - Server Configuration**. Click the **Synchronize** link and select **Synchronize** after being redirected.
17. Configure data cleansing configuration parameters:
- a) Select **Site Map > Administration > Data Quality > Third Party Administration**. On the Vendor Applet, include the ff value

Name	DLL Name
G1Cleansing	Group1Connector

b) Add the ff BC Vendor Field Mapping:

**Table 9: Siebel Business**

Business Component	Operation
Account	Data Cleansing
Business Address	Data Cleansing
Contact	Data Cleansing
List Mgmt Prospective Contact	Data Cleansing
Personal Address	Data Cleansing

**Table 10: Siebel Industry**

Business Component	Operation
Account	Data Cleansing
CUT Address	Data Cleansing
Contact	Data Cleansing
List Mgmt Prospective Contact	Data Cleansing
Personal Address	Data Cleansing

c) Under each BC operation, add the ff field mappings:



**Table 11: Siebel Business**

Business Component Field	Mapped Field
<b>Account</b>	
Name	FirmName
<b>Business Address</b>	
City	City
Country	CountryName
County	USCountyName
Disable DataCleansing	DisableDataCleansing
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Location Code	LocationCode
G1 Longitude	Longitude
G1 Match Code	MatchCode
G1 Residential Delivery Indicator	RDI
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2
<b>Contact</b>	
First Name	FirstName

Business Component Field	Mapped Field
Last Name	LastName
M/M	TitleOfRespect
Middle Name	MiddleName
<b>List Management Prospective Contact</b>	
City	City
Country	CountryName
County	USCountyName
Disable DataCleansing	DisableDataCleansing
First Name	FirstName
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Location Code	LocationCode
G1 Longitude	Longitude
G1 Match Code	MatchCode
G1 Residential Delivery Indicator	RDI
Last Name	LastName
Middle Name	MiddleName
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1

Business Component Field	Mapped Field
Street Address 2	AddressLine2
<b>Personal Address</b>	
City	City
Country	CountryName
County	USCountyName
Disable DataCleansing	DisableDataCleansing
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Longitude	Longitude
G1 Residential Delivery Indicator	RDI
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2

**Table 12: Siebel Industry**

Business Component Field	Mapped Field
<b>Account</b>	
Name	FirmName
<b>CUT Address</b>	
City	City

Business Component Field	Mapped Field
Country	CountryName
County	USCountyName
Disable Data Cleansing	DisableDataCleansing
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Location Code	LocationCode
G1 Longitude	Longitude
G1 Match Code	MatchCode
G1 Residential Delivery Indicator	RDI
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2
<b>Contact</b>	
First Name	FirstName
Last Name	LastName
Middle Name	MiddleName
M/M	TitleOfRespect
<b>List Management Prospective Contact</b>	
City	City

Business Component Field	Mapped Field
Country	CountryName
County	USCountyName
Disable DataCleansing	DisableDataCleansing
First Name	FirstName
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Location Code	LocationCode
G1 Longitude	Longitude
G1 Match Code	MatchCode
G1 Residential Delivery Indicator	RDI
Last Name	LastName
Middle Name	MiddleName
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2
<b>Personal Address</b>	
City	City
Country	CountryName
County	USCountyName

Business Component Field	Mapped Field
Disable DataCleansing	DisableDataCleansing
G1 Delivery Point Validation Indicator	DPV
G1 Latitude	Latitude
G1 Longitude	Longitude
G1 Residential Delivery Indicator	RDI
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2

d) Add the ff Vendor Parameters.

**Table 13: Siebel Business**

Name	Value
Account DataCleanse Record Type	Account
Business Address DataCleanse Record Type	Business Address
Contact DataCleanse Record Type	Contact
List Mgmt Prospective Contact DataCleanse Record Type	List Mgmt Prospective Contact
Personal Address DataCleanse Record Type	Personal Address

**Table 14: Siebel Industry:**

Name	Value
Account DataCleanse Record Type	Account
CUT Address DataCleanse Record Type	CUT Address
Contact DataCleanse Record Type	Contact
List Mgmt Prospective Contact DataCleanse Record Type	List Mgmt Prospective Contact
Personal Address DataCleanse Record Type	Personal Address

- e) Select **Site Map > Administration - Data Quality > Third Party Administration > Data Quality Settings**. Add the ff data for Data Quality Settings. These settings enable data cleansing for your Siebel Application

Name	Value
Enable DataCleansing	Yes

18. Configure data matching configuration parameters:

- a) Select **Site Map > Administration > Data Quality > Third Party Administration**. On the Vendor Applet, include the ff value

Name	DLL Name
G1DataMatching	Group1Connector

- b) Add the ff BC Vendor Field Mapping:

**Table 15: Siebel Business Applications**

Business Component	Operation
Account	DeDuplication
Business Address	DeDuplication

Business Component	Operation
Contact	DeDuplication
List Mgmt Prospective Contact	DeDuplication

**Table 16: Siebel Industry Applications**

Business Component	Operation
Account	DeDuplication
CUT Address	DeDuplication
Contact	DeDuplication
List Mgmt Prospective Contact	DeDuplication

- c) Under each BC operation, add the ff Field Mappings.

**Table 17: Siebel Business Applications**

Business Component Field	Mapped Field
<b>Account</b>	
Dedup Token	DedupToken
Id	Id
Location	Location
Name	Name
Primary Account City	City
Primary Account Country	CountryName
Primary Account Postal Code	PostalCode



Business Component Field	Mapped Field
Primary Account State	StateProvince
Primary Account Street Address	AddressLine1
<b>Business Address</b>	
City	City
Country	CountryName
Id	Id
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2
<b>Contact</b>	
First Name	FirstName
Id	Id
Last Name	LastName
Middle Name	MiddleName
Primary Account Name	AccountName
Primary City	City
Primary Country	CountryName
Primary Postal Code	PostalCode
Primary State	StateProvince

Business Component Field	Mapped Field
<b>List Management Prospective Contact</b>	
Account	Account
City	City
Country	CountryName
First Name	FirstName
Id	Id
Last Name	LastName
Middle Name	MiddleName
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2

**Table 18: Siebel Industry Applications**

Business Component Field	Mapped Field
<b>Account</b>	
Dedup Token	DedupToken
Id	Id
Location	Location
Name	Name
Primary Account City	City

Business Component Field	Mapped Field
Primary Account Country	Country
Primary Account Postal Code	PostalCode
Primary Account State	State
Primary Account Street Address	AddressLine1
<b>CUT Address</b>	
City	City
Country	Country
Id	Id
Postal Code	PostalCode
State	State
Street Address	AddressLine1
Street Address 2	AddressLine2
<b>Contact</b>	
First Name	FirstName
Id	Id
Last Name	LastName
Middle Name	MiddleName
Primary Account Name	Name
Primary City	City
Primary Country	Country

Business Component Field	Mapped Field
Primary Postal Code	Code
Primary State	State
<b>List Management Prospective Contact</b>	
Account	Account
City	City
Country	CountryName
First Name	FirstName
Id	Id
Last Name	LastName
Middle Name	MiddleName
Postal Code	PostalCode
State	StateProvince
Street Address	AddressLine1
Street Address 2	AddressLine2

d) Add the ff Vendor Parameters:

**Note:** Token Expression and Query Expression are custom fields in their respective Business Components.

**Table 19: Vendor Parameters**

Name	Value
Account DeDup Record Type	Account

Name	Value
Account Query Expression	" " + [Query Expression 1] + [Query Expression 2] + [Query Expression 3]
Account Token Expression	" " + [Token Expression 1] + [Token Expression 2] + [Token Expression 3]
Batch Max Num of Records	200
(Siebel Business Only) Business Address DeDup Record Type	Business Address
(Siebel Industry Only) CUT Address DeDup Record Type	CUT Address
Contact DeDup Record Type	Contact
Contact Query Expression	" " + [Query Expression 1] + [Query Expression 2] + [Query Expression 3]
Contact Token Expression	" " + [Token Expression 1] + [Token Expression 2] + [Token Expression 3]
List Mgmt Prospective Contact DeDup Record Type	List Mgmt Prospective Contact
List Mgmt Prospective Contact Query Expression	" " + [Query Expression 1] + [Query Expression 2] + [Query Expression 3]
List Mgmt Prospective Contact Token Expression	" " + [Token Expression 1] + [Token Expression 2] + [Token Expression 3]
Realtime Max Num of Records	200

- e) Select **Site Map > Administration - Data Quality > Third Party Administration > Data Quality Settings**. Add the ff data for Data Quality Settings. These settings enable data matching for your Siebel Application.

Name	Value
Enable DeDuplication	Yes


Name	Value
Force User DeDupe - Account	Yes
Force User DeDupe - Contact	Yes
Force User DeDupe - List Mgmt	Yes

19. (Open UI Only) Grant the EAI File Transport business service access to the file system by following these steps.

- a) Click **Navigate > Site Map**.
- b) Click **Administration - Server Configuration**.
- c) In the **Administration - Server Configuration** section, under **Enterprises**, click **Parameters**.
- d) Click **Query**.
- e) In the **Name** column, enter `EAI File Transport Folder List`.
- f) Click **Go**.
- g) In the **Value** column, enter the root of the drive where you have Siebel installed. For example, `C:\`.
- h) Click the **Servers** link:



- i) Click the **Parameters** tab:



- j) Click **Query**.
- k) In the **Name** column, enter EAI File Transport Folder List.
- l) Click **Go**.
- m) In the **Value** column, enter the root of the drive where you have Siebel installed. For example, C:\.
- n) Add the following values to the .cfg file appropriate for your system (for example, auto.cfg, tools.cfg, and so on).

```
[EAIFileTransportConfigSubsys]
EAIFileTransportFolders=C:\
```

- o) Restart the Siebel server and gateway.
20. Set the EditProfileAttr parameter:
- a) Click **Navigate > Site Map**
  - b) Click **Administration - Server Configuration**.
  - c) In the **Administration - Server Configuration** section, under **Servers**, click **Components**.
  - d) On the **Components** tab, click **Query**.
  - e) In the **Component** column, enter the name of the Object Manager component. For example, "eAutomotive Object Manager".
  - f) Click **Go**.
  - g) Click the **Parameters** tab at the bottom of the window.

The screenshot shows the Siebel Administration console interface. At the top, there are navigation tabs: Home, Accounts, Warranty Claims, Contacts, List Management, and Administration - Group 1 Data Quality. Below these are sub-tabs: Enterprise Explorer, Enterprises, Servers, and Job Templates. The main content area is divided into sections:

- Siebel Servers:** Contains a table with columns: Name, Server Group Name, Host Name. One row is visible: SBA82, (empty), Spectrum7Siebel, C:\Siebel\8.1.1.11.0\ses\siebsrvr.
- Components:** Contains sub-tabs: Components, Parameters, Events. Below are buttons: Menu, Query, Auto Start, Manual Start. A table with columns: Component, Alias. One row is visible: eAutomotive Object Manager (ENU), eautoObjMgr\_enu, eAutomotive.
- Events:** Contains a sub-tab: Parameters (highlighted with a red box and a red arrow pointing to it). Below are buttons: Menu, Query. A table with columns: Event Type, Log Level. Two rows are visible: EAI BusComp State Service (Log Level 1), EAI CRM Create Workitem (Log Level 1).

- h) Scroll to the parameter EditProfileAttr.
- i) Enter `True` in the **Value**, **Value on Restart**, and **Default Value** columns.

You have now configured Siebel SDQ to use Spectrum™ Technology Platform for data quality processing.



## Integrating with Siebel Non-SDQ

To integrate Spectrum™ Technology Platform with Siebel Non-SDQ, you need to install supporting databases and dataflows on the Spectrum™ Technology Platform server, and then configure your Siebel system to communicate with Spectrum™ Technology Platform. Once you do this, users of Siebel Non-SDQ will have access to address validation and geocoding functionality from within Siebel Non-SDQ.

1. On the Spectrum™ Technology Platform server, install the databases required to perform address validation, geocoding, and tax jurisdiction assignment and define database resources for each database.

You must give the database resources the following names.

Database	Required Name for Database Resource
Enterprise Geocoding Module - Canada Database	IGEO_CAN
Enterprise Geocoding Module - U.S. Database	EGM_US
Enterprise Tax Module Database	ETM
Universal Addressing Module - Canada Database	Canada
Universal Addressing Module - Loqate Database	Loqate
Universal Addressing Module - U.S. Database	UAM_US

2. When you install the Siebel module, several dataflow files are automatically installed. Other dataflow files must be manually copied into the Spectrum™ Technology Platform server.

a) Browse to one of the following folders on your Spectrum™ Technology Platform server:

- For Siebel Business Applications, go to:  
`<SpectrumPlatformLocation>\server\modules\dataflows\siebel\sea`
- For Siebel Industry Applications, go to:  
`<SpectrumPlatformLocation>\server\modules\dataflows\siebel\sia`

b) Review the following table then copy the applicable dataflow files to:

`SpectrumLocation\server\app\import`

**Table 20: Dataflow Files To Import**

If you are installing this set of modules Copy these dataflow files to the import folder

Address Now Module only	SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.ADN.df
Address Now Module Universal Addressing Module	SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.UAM_ADN.df
Address Now Module Enterprise Geocoding Module	GeocodeUSAddressWithCandidates.df SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.EGM_ADN.df
Address Now Module Enterprise Geocoding Module Universal Addressing Module	GeocodeUSAddressWithCandidates.df SiebelGetGlobalCandidateAddresses.df ValidateAddressWithCandidates.UAM_EGM_ADN.df
Universal Addressing Module only	ValidateAddressWithCandidates_UAM.df
Universal Addressing Module Enterprise Geocoding Module	GeocodeUSAddressWithCandidates.df ValidateAddressWithCandidates_UAM_EGM.df
Universal Addressing Module Enterprise Tax Module	GeocodeUSAddressWithCandidates.df ValidateAssignGeoTAXInfo.df ValidateAddressWithCandidates_UAM_ETM.df
Universal Address Module with Loqate	ValidateAddressWithCandidates_UAM_Loqate.df
Universal Addressing Module with Loqate Enterprise Geocoding Module	ValidateAddressWithCandidates_Loqate_EGM.df

If you are installing this set of modules Copy these dataflow files to the import folder

Universal Addressing Module, Loqate only Enterprise Geocoding Module	ValidateAddressWithCandidates_Loqate_EGM.df
Universal Addressing Module with Loqate Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_ETM.df
Universal Addressing Module with Loqate Enterprise Geocoding Module Enterprise Tax Module	ValidateAddressWithCandidates_UAM_Loqate_EGM_ETM.df
Universal Addressing Module, Loqate only	ValidateAddressWithCandidates_Loqate.df
Enterprise Geocoding Module	ValidateAddressWithCandidates_EGM.df
Enterprise Tax Module	ValidateAssignGeoTAXInfo.df
Global Addressing Module	SiebelGlobalTypeAhead.df

**Note:** If errors occur in Management Console or Enterprise Designer, delete the client cache. To delete the client cache, go to **Tools > Options** in Management Console or Enterprise Designer, click the **Advanced** tab, then click **Clear Cache**. After you clear the cache, restart Management Console or Enterprise Designer.

3. Optional: If you are using the Enterprise Geocoding Module, configure the geocoding dataflow to use the geocoding database resource name you have configured on your system:
  - a) In Enterprise Designer, open the dataflow GeocodeUSAddressWithCandidates.
  - b) In each dataflow, open the Geocode US Address stage.
  - c) In the **Database** field, select the name of the geocoding database as defined in the Management Console. The default name is KGDDatasource but if the geocoding database has a different name on your system, select the appropriate name.

**Note:** For more information about database resources, see the *Spectrum™ Technology Platform Administration Guide*.

- d) Save and close each dataflow.
4. Copy Siebel objects to your system:
  - a) Browse to the location where you downloaded the Spectrum™ Technology Platform installer.
  - b) Browse to the appropriate folder for your version of Siebel as shown in the following table.

Siebel Version	Folder
Siebel Business Applications 8.0 Non-SDQ	Siebel Objects\8.0\Business\non SDQ
Siebel Business Applications 8.1.1 Non-SDQ	Siebel Objects\8.1.1\Business\non SDQ
Siebel Industry Applications 8.0 Non-SDQ	Siebel Objects\8.0\Industry\non SDQ
Siebel Industry Applications 8.1.1 Non-SDQ	Siebel Objects\8.1.1\Industry\non SDQ

- c) Copy the contents of the folder to a temporary directory.

**Note:** This temporary folder will be referred to as `<Spectrum Package>` in the following steps.

5. Create objects and allow object locking:
  - a) Log in to Siebel Tools as the user SADMIN, with the connection pointing to the server data source.
  - b) Go to **Object Explorer**, drill down to the **Project** object. From the Project area, right-click and select **New Record**. Create the following projects:
    - Group 1 Data Quality
    - Group 1 EAI Testing
    - Group 1 Workflow
  - c) Open the file `<Spectrum Package>\tools\CDQP_Queries.txt`.
  - d) Copy and paste the query contents to the Project list of your Object Manager. Cross-check the query result with the table below and perform the action suggested. To toggle object locking, go to Object Explorer and browse to the Project object. From the Project area, right-click and select the project, and select **Toggle Object Locking**.

**Table 21: Queries for Siebel non-SDQ**

Siebel Business Applications	Siebel Industry Applications	Open UI	Project	Action
X	X	X	Account	Toggle Object Locking
X	X	X	Account (SCW)	Toggle Object Locking
X	X	X	Account (SSE)	Toggle Object Locking
X	X	X	Contact	Toggle Object Locking
X	X	X	Contact (SSE)	Toggle Object Locking
	X	X	CUT Account	Toggle Object Locking
	X	X	CUT Siebel Communications	Toggle Object Locking
	X	X	CUT Usage	Toggle Object Locking
X	X	X	DNB Data	Toggle Object Locking
X	X	X	DeDuplication	Toggle Object Locking
	X	X	eAutomotive	Toggle Object Locking
X	X	X	Employee	Toggle Object Locking
	X	X	FINS Contract	Toggle Object Locking

Siebel Business Applications	Siebel Industry Applications	Open UI	Project	Action
	X	X	FINS Contract Info	Toggle Object Locking
	X	X	FINS Deal Commercial	Toggle Object Locking
	X	X	FINS Financial Services	Toggle Object Locking
	X	X	FINS Opportunity	Toggle Object Locking
X	X	X	Group 1 Data Quality	Create and Toggle Object Locking
X	X	X	Group 1 EAI Testing	Create and Toggle Object Locking
	X	X	Group 1 Workflow	Create and Toggle Object Locking
X			List Mgmt (Import)	Toggle Object Locking
X	X	X	List Mgmt (UI)	Toggle Object Locking
X			Mvg	Toggle Object Locking
X	X	X	Oppty	Toggle Object Locking
X	X	X	Oppty (SSE)	Toggle Object Locking
X	X	X	Personal Contact	Toggle Object Locking
X	X	X	Picklist	Toggle Object Locking

Siebel Business Applications	Siebel Industry Applications	Open UI	Project	Action
X	X	X	Server Component Requests	Toggle Object Locking
X		X	Siebel Sales Enterprise	Toggle Object Locking
X			Siebel Universal Agent	Toggle Object Locking
	X	X	VERT CUT Address	Toggle Object Locking
	X	X	VERT Cut Common	Toggle Object Locking

6. Check out the Siebel Projects:

- a) Log in to Siebel Tools on Local Datasource.
- b) Select **Tools > Checkout**.
- c) Select the projects indicated in the following table and click **Checkout**.

**Table 22: Siebel Projects for non-SDQ**

Siebel Business Applications	Siebel Industry Applications	Project
X	X	Account
X	X	Account (SCW)
X	X	Account (SSE)
X	X	Contact
X	X	Contact (SSE)
	X	CUT Account
	X	CUT Siebel Communications
	X	CUT Usage

Siebel Business Applications	Siebel Industry Applications	Project
X	X	DNB Data
X	X	DeDuplication
	X	eAutomotive
X	X	Employee
	X	FINS Contract
	X	FINS Contract Info
	X	FINS Deal Commercial
	X	FINS Financial Services
	X	FINS Opportunity
X	X	Group 1 Data Quality
X	X	Group 1 EAI Testing
	X	Group 1 Workflow
X		List Mgmt (Import)
X	X	List Mgmt (UI)
X		Mvg
X	X	Oppty
X	X	Oppty (SSE)
X	X	Personal Contact
X	X	Picklist
X	X	Server Component Requests



Siebel Business Applications	Siebel Industry Applications	Project
X		Siebel Sales Enterprise
X		Siebel Universal Agent
	X	VERT CUT Address
	X	VERT Cut Common

7. Import the Spectrum™ Technology Platform Siebel objects:

- a) Select **Tools > Import from Archive**.
- b) Import the Siebel SIF files located in <Spectrum Package>\sif. Select **Overwrite the object definition in the repository** and click **Next** to proceed until the import process has been completed.

- G1\_NEW.sif
- G1\_APPLET.sif
- G1\_BO.sif
- G1\_LINK.sif
- G1\_BC.sif
- G1\_BC\_SCRIPTS.sif
- G1\_EAI\_TESTING.sif
- G1\_APPLICATION.sif
- G1\_PICKLIST.sif
- G1\_VIEW.sif
- G1\_WORKFLOW.sif
- (8.1.1 only) Rebranding.sif
- PB\_SecToken.sif

**Note:** *PB\_SecToken.sif* must be imported in the end.

- c) (Open UI Only) Import the Siebel SIF files located in <Spectrum Package>\OPEN\_UI. Select **Overwrite the object definition in the repository** and click **Next** to proceed until the import process has been completed.
  - FINS Personal Address List Applet.sif
  - G1 Common Browser Scripts Service.sif
  - Siebel Sales Enterprise.sif

8. Check in all locked projects:

- a) Select **Tools > Check In**.

- b) Select all the Projects to check in and click **Check in**.
9. Compile all Projects:
  - a) Select **Tools > Compile Projects**.
  - b) Click **All Projects**.
  - c) In the **Siebel Repository File** field, enter the path of your Siebel Web Client SRF file.
  - d) Click **Compile**.
10. Update the application .CFG file:
  - a) Open the appropriate .cfg file in an editor:

For example, for Siebel Business:

- Siebel Call Center—uagent.cfg
- Siebel Sales—siebel.cfg

For example, for Siebel Industry:

- eAutomotive—auto.cfg
- Financial—fins.cfg
- eCommunication—ecomm.cfg

Siebel .cfg files are usually found in the following locations:

- Siebel thick client—Siebel\<version>\web client\bin\enu
- Siebel thin client—<Siebel Server>\bin\enu

- b) Add the following lines under the [SWE] section:

```
ClientBusinessService0 = G1 Async Service
ClientBusinessService1 = G1 Business Name Standardization Service
ClientBusinessService2 = G1 Common Browser Scripts Service
ClientBusinessService3 = G1 Common Server Scripts Service
ClientBusinessService4 = G1 DNB VBC Service
ClientBusinessService5 = G1 Data Cleansing Service
ClientBusinessService6 = G1 DeDuplication Service
ClientBusinessService7 = G1 Generate HashKey Service
ClientBusinessService8 = G1 GeoCoding Service
ClientBusinessService9 = G1 Interactive Service
ClientBusinessService10 = G1 Merge Records Service
ClientBusinessService11 = G1 Name Casing Service
ClientBusinessService12 = G1WebService
```

11. Deploy the Siebel objects in the client:

**Note:** Keep a backup of the old SRF in case old binaries need to be re-implemented.

- a) Copy the generated SRF to your web client objects folder.

For example, on Windows this folder may be `C:\Program Files\Siebel\8.0\web client\OBJECTS\ENU`. On Unix or Linux this folder may be `/disk2/sia78/webclient/OBJECTS/enu/`.

- b) Open a command prompt and go to the BIN folder of the web client.

For example, on Windows this folder may be `C:\Program Files\Siebel\8.0\web client\BIN`. On Unix or Linux, this folder may be `/disk2/sia80/webclient/BIN`.

- c) Generate browser scripts by issuing this command:

On Windows:

```
genbscript "ENU\siebel.cfg" "[public\enu folder]"
```

On Unix or Linux:

```
genbscript [location of .cfg] [public/enu folder]
```

For example, on Windows:

```
C:\Program Files\Siebel\8.0\web client\BIN>genbscript
"enu\siebel.cfg" "C:\Program Files\Siebel\8.0\web client\PUBLIC\enu"
```

On Unix or Linux:

```
genbscript /disk2/sia80/webclient/BIN/enu/siebel.cfg
sia80/webclient/PUBLIC/enu
```

- d) Copy `g1_check.gif` and `g1_x.gif` from the temporary folder to `public\enu\images` in the Siebel web client.
- e) Copy the contents of `<Spectrum Package>\dll` to your BIN folder.
- f) Copy the contents of `<Spectrum Package>\cfg` to your BIN/ENU folder.

## 12. Deploy the Siebel objects to the server:

- a) Stop the Siebel server.
- b) Copy the generated SRF file to your web client objects folder.

For example, the folder for Siebel Business on Windows may be `C:\sea80\siebsrvr\OBJECTS\ENU`. On Unix or Linux the folder may be `/disk2/sea80/siebsrvr/OBJECTS/enu/`.

- c) Open a command prompt and go to the BIN drive of the web client.

For example, on Windows this folder may be `C:\sia80\siebsrvr\BIN`. On Unix or Linux this folder may be `/disk2/sea80/siebsrvr/BIN`.

- d) Generate browser scripts by issuing this command:

On Windows:

```
genbscript "ENU\siebel.cfg" "[webmaster folder]"
```

On Unix or Linux:

```
genbscript [location of Siebel.cfg] [webmaster folder]
```

For example, on Windows:

```
C:\sia80\siebsrvr\BIN>genbscript "enu\siebel.cfg"
"C:\sia80\siebsrvr\WEBMASTER"
```

For example, on Unix or Linux:

```
genbscript /disk2/sea80/siebsrvr/BIN/enu/siebel.cfg
/disk2/sea80/siebsrvr/WEBMASTER/
```

- e) Copy `g1_check.gif` and `g1_x.gif` from the temporary folder to the following folder on the Siebel sever.

On Windows:

```
public\enu\images
```

On Unix or Linux:

```
WEBMASTER/images/enu
```

**Note:** For Siebel Thin Client, copy `g1_check.gif` and `g1_x.gif` from the temporary directory to `SWEApp/PUBLIC/enu/images`.

- f) Copy the generated browser scripts from `/WEBMASTER` to `<SWEApp Location>/public/ENU`.
- g) Start the Siebel server.

13. Activate the Spectrum™ Technology Platform workflows in the Siebel web client:

- a) Log in to the Siebel application, connecting to the server data source.
- b) Select **Site Map > Administration - Business Process > Workflow Deployment**.
- c) Query for all the GROUP 1\* workflows.
- d) Click **Activate** for each workflow.
- e) Query for all the Promote\* workflows.
- f) Click **Activate** for the ff workflows **Promote Prospect (Single)** and **Promote Prospect (Many)**.
- g) Click **Import Process** in the **Menu** option in the **Active Workflow Process** screen. Specify the file `<Spectrum Package>\workflows\PB Token WS Workflow.xml`.

14. Load the Group 1 configuration.

- a) Log in to the Siebel application connecting to the server data source.
- b) Go to **Site Map > Administration - Business Service > Simulator**.
- c) In the top applet, create a new record and set the following fields:

Service Name	Workflow Process Manager
Method Name	Run Process
Iterations	1

- d) In the Input Arguments applet, load:

```
<Spectrum Package>\tools\OptionsManagerLoadData.xml
```

**Note:** Delete the entry if previous GROUP 1 options already exist in the database.  
Run the following SQL Script: `DELETE SIEBEL.S_LST_OF_VAL WHERE CODE = 'G1'`

- e) Click **Run** in the top applet of the Simulator view. Delete the record.

- f) Repeat steps c. and d. for the ff files:

- ViewAccessLoadData.xml
- AdminAccessLoadData.xml

- g) Go to **Site Map > Administration - Application > Responsibilities:**

- h) Query for the responsibility Group 1 Responsibility.

- i) In the Users tab, add SADMIN or any Siebel administrator. This associates the Group 1 Administration Screen to the user.

**Note:** In order to see the changes you must log-in again.

- j) Go to **Site Map > Administration - Group 1 Data Quality > Options Manager > General Behavior.**

- k) Change the server and port number where the Spectrum™ Technology Platform server is located.

15. Verify the installation:

- a) Log in to Siebel Application.
- b) All applets should load properly without error.

16. Modify and apply web services.

- a) Go to **Site Map > Administration - Web Services > Outbound Web Services.**

- b) Click **Import** on the **Outbound Web Services** area and then specify the file `<Spectrum Package>\webservices\G1WebService.xml`.

- c) Query on the Name field ValidateAddress, and modify its settings as follows:

On the Service Port applet, change the following fields:

- Transport: Local Business Service
- Address: G1 WebService Filter Service

On the Operations applet, change the following fields:

- Response Filter Service Display: G1 WebService Filter Service
- Response Filter Method Display: filter Response

- d) Click **Import** on the **Outbound Web Services** area and then specify the file `<Spectrum Package>\webservices\TokenManagerServiceImplService.xml`.

17. Encrypt and apply Spectrum™ Technology Platform user name and password.

- a) Run the following command on the command prompt:

```
java -version
```

Java Runtime Environment (JRE) 1.4.x is required. If none is installed, you can download from [java.sun.com/j2se/1.4.2/download.html](http://java.sun.com/j2se/1.4.2/download.html). Download the JRE of your target platform.

- b) Acquire the file `<Spectrum Package>\tools\Base64.class`.  
 c) On the command prompt, type the following command:

```
java Base64 -encode -s "<username>:<password>"
```

where `<username>` and `<password>` is to the login information of Spectrum™ Technology Platform server. Copy the generated value.

**Note:** The default Spectrum™ Technology Platform password can be found in `<Spectrum Package>\tools\Default Password.txt`.

- d) Go to **Site Map > Administration - Group 1 Data Quality > Password Manager**. Paste the value generated in step c. and click **Save Changes**.

18. Configure Siebel server configuration events.

The Siebel server must be configured so that the records created in the local database can be synchronized to the server.

- a) Navigate to **View > Administration - Server Configuration > Servers > Components > Event**.  
 b) Locate the Workflow Process Manager Server components.  
 c) Set the following Component Event Configuration for Workflow Process Manager:

Task Configuration	4
Component Tracing	3
SQL Parse and Execute	4
Workflow Definition Loading	4

Workflow Engine Invoked	4
Workflow Step Execution	4
Workflow Process Execution	4
Object Manager Business Service Operation and SetErrorMsg Log	4
Object Manager Business Component Operation and SetErrorMsg Log	4
Object Manager SQL Log	4

- d) Locate the Transaction Merger server components.  
e) Set the following Component Event Configuration for Transaction Merger:

General Events	4
Components Tracing	3
SQL Parse and Execute	4

#### 19. Enable marketing server components.


The Marketing Server Components must be enabled to import a list from the List Management business object.

- Navigate to **Administration - Server Configuration > Enterprises > Component Groups**.
- In the Spectrum™ Technology Platform Server list, select the appropriate server.
- In the Enterprise Component Groups list, locate each of the required component groups using the following table. If the **Enable State** field does not contain the value **Enabled**, select the component groups, click the menu button, and choose **Enable Component Group**.


Group Name	Components	Description
MktgOM	<ul style="list-style-type: none"> <li>Marketing Obj Mgr</li> <li>eMarketing Obj Mgr</li> <li>eEvents Obj Mjr</li> </ul>	Marketing Object Manager. Supports the user interface and business objects for the Marketing application.

Group Name	Components	Description
Mktg Srv	List Import Service Manager	Marketing Server. Used for list management list import.

- d) Click the **Synchronize view** tab and click **Synchronize**.
  - e) Restart the Siebel server. The Siebel server must be restarted each time synchronization occurs.
20. (Open UI Only) Grant the EAI File Transport business service access to the file system by following these steps.
- a) Click **Navigate > Site Map**.
  - b) Click **Administration - Server Configuration**.
  - c) In the **Administration - Server Configuration** section, under **Enterprises**, click **Parameters**.
  - d) Click **Query**.
  - e) In the **Name** column, enter `EAI File Transport Folder List`.
  - f) Click **Go**.
  - g) In the **Value** column, enter the root of the drive where you have Siebel installed. For example, `C:\`.
  - h) Click the **Servers** link:



- i) Click the **Parameters** tab:





- j) Click **Query**.
- k) In the **Name** column, enter `EAI File Transport Folder List`.
- l) Click **Go**.
- m) In the **Value** column, enter the root of the drive where you have Siebel installed. For example, `C:\`.
- n) Add the following values to the `.cfg` file appropriate for your system (for example, `auto.cfg`, `tools.cfg`, and so on).

```
[EAIFileTransportConfigSubsys]
EAIFileTransportFolders=C:\
```

- o) Restart the Siebel server and gateway.

21. Set the `EditProfileAttr` parameter:

- a) Click **Navigate > Site Map**
- b) Click **Administration - Server Configuration**.
- c) In the **Administration - Server Configuration** section, under **Servers**, click **Components**.
- d) On the **Components** tab, click **Query**.
- e) In the **Component** column, enter the name of the Object Manager component. For example, "eAutomotive Object Manager".
- f) Click **Go**.
- g) Click the **Parameters** tab at the bottom of the window.

The screenshot shows the Siebel Servers configuration interface. The 'Servers' tab is active, displaying a table with the following data:

Name	Server Group Name	Host Name	
SBA82		Spectrum7Siebel	C:\Siebel8.1.1.11.0\ses\siebsrvr

Below the servers table, the 'Components' tab is active, displaying a table with the following data:

Component	Alias	
eAutomotive Object Manager (ENU)	eautoObjMgr_enu	eAutomotive

A red arrow points to the 'Parameters' button in the 'Events' section below the components table.

- h) Scroll to the parameter EditProfileAttr.
- i) Enter `True` in the **Value**, **Value on Restart**, and **Default Value** columns.

22. (Siebel Open UI only) Configure the **Type Ahead** feature using these steps:

**Note:** This feature requires acquiring the license of the **Global Addressing Module**. Also, you need to enable CORS on the Spectrum server for accessing **Type Ahead** service. For details see the **Security** chapter in the Spectrum Administration Guide.

a) On the Siebel web server, go to <SWEApp>\PUBLIC\enu, and copy these files located in <Spectrum Package>\OPEN\_UI folder to the PUBLIC\enu folder.

- pb-bootstrap.min.js
- pb-bootstrap-combined.min.css

**Note:** In case of Siebel IP 16, copy the files to <SWEApp>\PUBLIC.

b) Copy these files from <Spectrum Package>\OPEN\_UI to <SWEApp>\PUBLIC\enu\<buildnumber>\scripts\siebel\custom and <SIEBEL ROOT>\Siebsrvr\WEBMASTER\<buildnumber>\scripts\siebel\custom.

- AccountAddressAutoCompletePR.js
- ContactAddressAutoCompletePR.js

**Note:** In case of Siebel IP 16, copy the files to <SWEApp>\PUBLIC\enu\scripts\siebel\custom.

c) In the **Siebel** application, go to **Administration- Application > Manifest Files** and add these files:

- siebel/custom/AccountAddressAutoCompletePR.js
- siebel/custom/ContactAddressAutoCompletePR.js

d) Go to **Administration - Application > Manifest Administration**, and perform PR configuration for these applets and associate the manifest files added in the previous step.

- Account Address Mvg Applet
- Contact Personal Address Mvg Applet

You have now configured Siebel non-SDQ to use Spectrum™ Technology Platform for data quality processing.

## Compatibility Matrix

This tables give a list of various Siebel versions supported for installation or upgrade by Spectrum™ Technology Platform 10.x, 11.x, and 12.x versions.

**Table 23: Compatibility Matrix for New Installation**

Spectrum Version	Supported Siebel Version
10.x	SBA 8.0, SIA 8.0, SBA 8.1, SIA 8.1, Siebel Open UI (8.1.1.11)

Spectrum Version	Supported Siebel Version
11.x	SBA 8.0, SIA 8.0, SBA 8.1, SIA 8.1, Siebel Open UI (8.1.1.11)
12.x	SBA 8.0, SIA 8.0, SBA 8.1, SIA 8.1, Siebel Open UI (8.1.1.11), Siebel IP 16

**Note:** It is recommended that you contact the Pitney Bowes representative or coordinator assigned to you before starting the process of upgrade/installation.

## Configuring SugarCRM

### Integrating with SugarCRM

To integrate Spectrum™ Technology Platform with SugarCRM, you must install the supporting databases and dataflows on the Spectrum™ Technology Platform server, and deploy the Spectrum™ Technology Platform solution on your SugarCRM. Once you do this, users of SugarCRM will have access to address validation, geocoding, and duplicate detection functionality from within SugarCRM.

#### Before you begin:

#### Entities Supported:

You can validate and geocode the addresses of the entities:

1. Accounts
2. Contacts
3. Leads

#### Supported SugarCRM Versions

##### *SugarCRM 7.7.1.1*

Browse to the the folder "Sugar CRM DQ Objects\sugarcrm" in the Spectrum™ Technology Platform installation package and copy the file `PBSugarCRMConnector.zip` to any location on your SugarCRM server.

1. If you are using Spectrum™ Technology Platform for address validation or geocoding, install the databases required to perform address validation and geocoding and define database resources for each database.

**Note:** If you are using Spectrum™ Technology Platform for duplicate detection only, you can skip this step.

You must give the database resources these names:

Database	Required Name for Database Resource
Enterprise Geocoding Module - Canada Database	IGEO_CAN
Enterprise Geocoding Module - U.S. Database	EGM_US
Universal Addressing Module - Canada Database	Canada
Universal Addressing Module - Loqate Database	Loqate
Universal Addressing Module - U.S. Database	UAM_US

**Note:** You must install the Delivery Point Validation (DPV) data and the Residential Delivery Indicator (RDI) data in order to perform DPV and RDI processing on U.S. addresses.

2. Import the SugarCRM Module dataflows into your Spectrum™ Technology Platform server.

a) On the Spectrum™ Technology Platform server, open this folder:

*SpectrumFolder\server\modules\sugarcrm*

**Note:** This folder is only available if you have installed the SugarCRM Module.

b) As mentioned in the table below, copy the applicable dataflow files to the *import* folder:

*SpectrumFolder\server\app\import*

If you have installed this set of modules Copy these dataflow files to the import folder

Advanced Matching Module	<i>GenerateMatchKey.df</i> <i>GenerateMatchScore.df</i> <i>GenerateSearchKey.Consonant.df</i> <i>GenerateSearchKey.df</i> <i>GenerateSearchKey.Metaphone.df</i> <i>GenerateSearchKey.Substring.df</i>
Universal Addressing Module without Loqate	<i>ValidateAddresswithCandidates_UAM.df</i>

If you have installed this set of modules Copy these dataflow files to the import folder

Universal Addressing Module without Loqate Enterprise Geocoding Module	<i>ValidateAddressWithCandidates_UAM_EGM.df</i>
Universal Addressing Module with Loqate	<i>ValidateAddressWithCandidates_UAM_Loqate.df</i>
Universal Addressing Module with Loqate Enterprise Geocoding Module	<i>SugarCRMValidateAddressAndGenerateMatchKey.df</i> <i>ValidateAddressWithCandidates_UAM_Loqate_EGM.df</i>
Universal Addressing Module, Loqate only	<i>ValidateAddressWithCandidates_Loqate.df</i>
Universal Addressing Module, Loqate only Enterprise Geocoding Module	<i>ValidateAddressWithCandidates_Loqate_EGM.df</i>
Enterprise Geocoding Module	<i>GeocodeUSAddressWithCandidates.df</i>

3. Import the Pitney Bowes SugarCRM module into your SugarCRM system.
  - a) Log in to SugarCRM as an administrator.
  - b) In the profile dropdown at the top right corner, click **Admin**.
  - c) In this **Administration** screen, in the **Developer Tools** section, click **Module Loader**. The **Module Loader** screen opens.
  - d) If you are integrating your SugarCRM system with Spectrum™ Technology Platform for the first time, you must upload the SugarCRM Connector module of your SugarCRM system:
    1. Upload the ZIP file *PBSugarCRMConnector.zip* of Spectrum copied earlier to the system, using the file uploader field in the centre of the page.
    2. Click **Upload**.
    3. Click **Confirm**. An entry for the *Pitney Bowes* package now shows in the bottom grid.
  - e) Once the *Pitney Bowes* package is uploaded into the system, or if it has been uploaded previously into your SugarCRM system but is uninstalled:

1. Click **Install** against the Pitney Bowes package entry in the bottom grid on the **Module Loader** screen.
  2. On the **Licence** screen, select **Accept**, then click **Commit**.
- f) In the profile dropdown at the top right corner, click **Admin**.
  - g) In this **Administration** screen, in the **System** section, click **Repair**.  
The **Repair** screen opens.
  - h) Click **Quick Repair and Build**.  
The existing SugarCRM configurations are rebuilt to incorporate the custom Objects and Object Layouts imported with the SugarCRM Connector module. The logs are displayed.

Spectrum's SugarCRM Connector module is now successfully integrated with your SugarCRM system.

The menu item **Administration > PB Service Configuration** is now available.

## Creating a Connection to Spectrum

Once the SugarCRMConnector module of Spectrum™ Technology Platform is uploaded successfully in your SugarCRM, you can create a connection to the Spectrum server.

1. Login to your SugarCRM system as an Administrator.
2. Go to **Administration > PB Service Configuration**.
3. Click **Create**.
4. In the **Name** field, enter the desired name for the connection. For example, `PB_SpectrumConnection`.
5. In the **Server Name** field, enter the server name or IP address of the Spectrum™ Technology Platform server.
6. In the **Port** field, enter the port used by the Spectrum™ Technology Platform server for HTTP communication. By default the port is `8080`.
7. In the **User Name** field, enter the Spectrum™ Technology Platform user name.
8. In the **Password** field, enter the password for the Spectrum™ Technology Platform user.
9. If you wish to run the duplicate detection feature provided by the Pitney Bowes Address Validation bundle:
  - Check **Duplicate Detection**.
  - In the **Threshold** field, enter a value between 0 and 100, both inclusive. If you leave this field blank, the default threshold value of 30 is used. The Pitney Bowes Address Validation service fetches those records as duplicate whose match score is equal to or higher than the *threshold* match score.

For more information, see [Threshold](#).

10. Before saving the connection, click **Test Connection** to verify the entered credentials for the Spectrum server.

11. Once the Spectrum connection details are tested successfully, click **Save**.

**Note:** You can either test a connection before clicking **Save**, or test an existing connection by first opting to **Edit** it.

You can now use this connection to validate and geocode the addresses of records in your SugarCRM system using the Spectrum™ Technology Platform.

**Note:** Only one connection to the Spectrum™ Technology Platform can exist at a time. To create another connection to Spectrum™ Technology Platform, you can either delete the existing connection and create a new one, or edit the existing connection.

## Configuring Microsoft Dynamics CRM

### Integrating with Spectrum™ Technology Platform

To integrate Spectrum™ Technology Platform with Spectrum™ Technology Platform, you must install the supporting databases and dataflows on the Spectrum™ Technology Platform server, and deploy the Spectrum™ Technology Platform solution on your Spectrum™ Technology Platform. Once you do this, users of Spectrum™ Technology Platform will have access to address validation, geocoding, and duplicate detection functionality from within Spectrum™ Technology Platform.

**Note:** End users who use Internet Explorer must use Internet Explorer 10 or 11. Older versions of Internet Explorer are not supported. All versions of Chrome and Firefox are supported.

Before you begin, confirm that you are using a compatible version of Microsoft Dynamics. These versions are supported:

Microsoft Dynamics CRM 2013  
Microsoft Dynamics CRM 2013 SP1  
Microsoft Dynamics 2015

1. If you are using Spectrum™ Technology Platform for address validation or geocoding, install the databases required to perform address validation and geocoding and define database resources for each database.

**Note:** If you are using Spectrum™ Technology Platform for duplicate detection only, you can skip this step.

You must give the database resources these names:



Database	Required Name for Database Resource
Enterprise Geocoding Module - Canada Database	IGEO_CAN
Enterprise Geocoding Module - U.S. Database	EGM_US
Universal Addressing Module - Canada Database	Canada
Universal Addressing Module - Loqate Database	Loqate
Universal Addressing Module - U.S. Database	UAM_US

**Note:** You must install the Delivery Point Validation (DPV) data and the Residential Delivery Indicator (RDI) data in order to perform DPV and RDI processing on U.S. addresses.

2. Import the Spectrum™ Technology Platform Module dataflows into your Spectrum™ Technology Platform server.

a) On the Spectrum™ Technology Platform server, open this folder:

*SpectrumFolder\server\modules\dataflows\mscrm*

**Note:** This folder is only available if you have installed the Spectrum™ Technology Platform Module.

b) As mentioned in the table below, copy the applicable dataflow files to the *import* folder:

*SpectrumFolder\server\app\import*

If you have installed this set of modules Copy these dataflow files to the import folder

Advanced Matching Module	<i>GenerateMatchKey.df</i> <i>GenerateMatchScore.df</i> <i>GenerateSearchKey.Consonant.df</i> <i>GenerateSearchKey.df</i> <i>GenerateSearchKey.Metaphone.df</i> <i>GenerateSearchKey.Substring.df</i>
Universal Addressing Module without Loqate	<i>ValidateAddresswithCandidates_UAM.df</i>

If you have installed this set of modules Copy these dataflow files to the import folder

Universal Addressing Module without Loqate Enterprise Geocoding Module	<i>ValidateAddressWithCandidates_UAM_EGM.df</i>
Universal Addressing Module with Loqate	<i>ValidateAddressWithCandidates_UAM_Loqate.df</i>
Universal Addressing Module with Loqate Enterprise Geocoding Module	<i>SugarCRMValidateAddressAndGenerateMatchKey.df</i> <i>ValidateAddressWithCandidates_UAM_Loqate_EGM.df</i>
Universal Addressing Module, Loqate only	<i>ValidateAddressWithCandidates_Loqate.df</i>
Universal Addressing Module, Loqate only Enterprise Geocoding Module	<i>ValidateAddressWithCandidates_Loqate_EGM.df</i>
Enterprise Geocoding Module	<i>GeocodeUSAddressWithCandidates.df</i>

3. Import the Microsoft Dynamics CRM Module into your Microsoft Dynamics CRM system.
  - a) In the Spectrum™ Technology Platform installation package, go to this folder:  
`MS CRM Objects\Proxy`
  - b) Copy the file `netProxy.aspx` to this folder on your Microsoft Dynamics CRM server:  
`MicrosoftDynamicsCRMInstallation\CRMWeb`
  - c) Copy the file `netProxy.dll` to this folder on your Microsoft Dynamics CRM server:  
`MicrosoftDynamicsCRMInstallation\CRMWeb\Bin`
  - d) Log in to Microsoft Dynamics CRM as an administrator.
  - e) Click **Microsoft Dynamics CRM** then click **Settings**.
  - f) Click **Solutions**.
  - g) Click **Import**.
  - h) Go to the Spectrum™ Technology Platform installation package and select the file:

MS CRM Objects\mscrm\PBMSDynamicsCRMConnector\_4\_0\_0\_managed.zip

- i) Click **Next** then **Publish All Customizations**.
  - j) Restart the Microsoft Dynamics CRM server.
4. Define the connection between Microsoft Dynamics CRM and the Spectrum™ Technology Platform server.
- a) Log in to Microsoft Dynamics CRM as an administrator.
  - b) Click **Microsoft Dynamics CRM > Settings**.
  - c) Click **Settings > Pitney Bowes**. You will have to scroll to the right to find the Pitney Bowes link.
  - d) Click **Administration**.
  - e) Click **New**.
  - f) In the **Name** field, enter `PB`.
  - g) In the **Server Name** field, enter the server name or IP address of the Spectrum™ Technology Platform server.
  - h) In the **Port** field, enter the port used by the Spectrum™ Technology Platform server for HTTP communication. By default the port is 8080.
  - i) In the **Account ID** field, enter the Spectrum™ Technology Platform user name.
  - j) In the **Password** field, enter the password for the Spectrum™ Technology Platform user.
  - k) Click **Save**

The Microsoft Dynamics CRM system now has access to address validation and, optionally, geocoding services on the Spectrum™ Technology Platform server.

# 9 - Support

## In this section

---

Support

173

# Support

## Technical Support

If you run into an issue, Pitney Bowes Technical Support can help guide you to a solution. When you contact Pitney Bowes Technical Support, please provide the following information:

- A description of the task you were performing
- The level or version of your operating system
- The patch level or service pack
- The log file located in your install directory at:

`<SpectrumInstallationLocation>\server\app\repository\logs\wrapper.log`

Contact information for Technical Support can be found at:

[support.pb.com/spectrum](https://support.pb.com/spectrum)

**Note:** If you purchased Spectrum™ Technology Platform through a third-party partner, please contact the partner for technical support.

## Documentation

Product documentation can be found at:

[support.pb.com/spectrum](https://support.pb.com/spectrum)

## Digital Insights

Digital Insights is an online resource for Pitney Bowes leadership to share innovations, goals, and product news, as well as exchange ideas with visitors. You can access Digital Insights at:

[blogs.pb.com/digital-insights/](https://blogs.pb.com/digital-insights/)

# Notices

© 2018 Pitney Bowes Software Inc. All rights reserved. MapInfo and Group 1 Software are trademarks of Pitney Bowes Software Inc. All other marks and trademarks are property of their respective holders.

### *USPS® Notices*

Pitney Bowes Inc. holds a non-exclusive license to publish and sell ZIP + 4® databases on optical and magnetic media. The following trademarks are owned by the United States Postal Service: CASS, CASS Certified, DPV, eLOT, FASTforward, First-Class Mail, Intelligent Mail, LACS<sup>Link</sup>, NCOA<sup>Link</sup>, PAVE, PLANET Code, Postal Service, POSTNET, Post Office, RDI, Suite<sup>Link</sup>, United States Postal Service, Standard Mail, United States Post Office, USPS, ZIP Code, and ZIP + 4. This list is not exhaustive of the trademarks belonging to the Postal Service.

Pitney Bowes Inc. is a non-exclusive licensee of USPS® for NCOA<sup>Link</sup>® processing.

Prices for Pitney Bowes Software's products, options, and services are not established, controlled, or approved by USPS® or United States Government. When utilizing RDI™ data to determine parcel-shipping costs, the business decision on which parcel delivery company to use is not made by the USPS® or United States Government.

### *Data Provider and Related Notices*

Data Products contained on this media and used within Pitney Bowes Software applications are protected by various trademarks and by one or more of the following copyrights:

- © Copyright United States Postal Service. All rights reserved.
- © 2014 TomTom. All rights reserved. TomTom and the TomTom logo are registered trademarks of TomTom N.V.
- © 2016 HERE
- Fuente: INEGI (Instituto Nacional de Estadística y Geografía)
- Based upon electronic data © National Land Survey Sweden.
- © Copyright United States Census Bureau
- © Copyright Nova Marketing Group, Inc.
- Portions of this program are © Copyright 1993-2007 by Nova Marketing Group Inc. All Rights Reserved
- © Copyright Second Decimal, LLC
- © Copyright Canada Post Corporation
- This CD-ROM contains data from a compilation in which Canada Post Corporation is the copyright owner.
- © 2007 Claritas, Inc.

The Geocode Address World data set contains data licensed from the GeoNames Project ([www.geonames.org](http://www.geonames.org)) provided under the Creative Commons Attribution License ("Attribution

License") located at <http://creativecommons.org/licenses/by/3.0/legalcode>. Your use of the GeoNames data (described in the Spectrum™ Technology Platform User Manual) is governed by the terms of the Attribution License, and any conflict between your agreement with Pitney Bowes Software, Inc. and the Attribution License will be resolved in favor of the Attribution License solely as it relates to your use of the GeoNames data.





3001 Summer Street  
Stamford CT 06926-0700  
USA

[www.pitneybowes.com](http://www.pitneybowes.com)