



Spectrum Technology Platform

Version 2022.1.0 S16

Release Notes

This document contains information about Spectrum Technology Platform 2022.1.0 patch S16. You have access only to the modules you have licensed. To evaluate any other modules, contact your Precisely account executive for a trial license key.

| | |
|--------------------------------------|--|
| Who should apply this update? | This product update is intended for all Spectrum Technology Platform 2022.1.0 users. |
|--------------------------------------|--|

| | |
|---------------------------------|---|
| Is this update required? | This product update is required if the Context Graph module is installed with the Spectrum Technology Platform. |
|---------------------------------|---|

Contents:

| | |
|-------------------|---|
| Fixed Issues..... | 2 |
| Installation..... | 2 |



Fixed Issues

This product update fixes the issue in the Context Graph module:

CDQE-99170 Cannot coerce INTEGER to Java int without losing precision when loading outgoing entities on Visualization canvas.

Installation

To install this product update you must have Spectrum Technology Platform 2022.1.0 installed.

Important: Before you install this product update, be sure that you have installed all previously released product updates for your modules and the platform. Unexpected issues may occur if you do not install product updates in the proper order. For a listing of product updates for each module and the platform, see the [Product Update Summary](#).

Applying This Product Update to a Cluster

To apply this product update to a cluster you must stop all the nodes in the cluster then install the product update to each node by following the instructions in these release notes. You can start up each node after you update it.

Warning: You must shut down the cluster before installing this patch. Failure to do so may result in data loss and your system may become unusable.

Applying This Product Update to a Distributed Configuration

To apply this product update to a distributed configuration you must stop all repository instances and server instances of Precisely Spectrum Technology Platform. Extract the patch to a separate directory. For the repository instances, follow the steps that apply to the `SpectrumDirectory/repository`. For the server instances, follow the other steps that apply to the server.

Installing on Windows

Follow these steps to install the Spectrum Technology Platform 2022.1.0 S16 patch in a Windows configuration.

Note: In this procedure, *SpectrumDirectory* is the directory where the Spectrum Technology Platform server is installed (for example, C:\Program Files\Precisely\Spectrum).

1. Stop the Spectrum Technology Platform server.
To stop the server, right-click the Spectrum Technology Platform icon in the Windows system tray and click **Stop Spectrum**.
2. Back up this file from *SpectrumDirectory* to a different location:

```
server\deploy\contextgraph-22.1.car
```
3. Use the link in the release announcement to download the ZIP file containing the product update. You can also find links to software, release notes, and checksum values on the [2022.1.0 Updates](#) page.
4. Extract the contents of the ZIP file to a temporary location.
5. Extract the contents of the resulting ZIP file (*cdq20221s16.zip*) to the directory where the Spectrum Technology Platform server is installed (*SpectrumDirectory*).
Choose to overwrite the existing files.
6. Start the Spectrum Technology Platform server.
To start the server, right-click the Spectrum Technology Platform icon in the Windows system tray and click **Start Spectrum**.

Installing on Linux

Follow these steps to install the Spectrum Technology Platform 2022.1.0 S16 patch in a Linux configuration.

Note: In this procedure, *SpectrumDirectory* is the directory where the Spectrum Technology Platform server is installed (for example, /home/user/myuser/Precisely/Spectrum).

1. Source the *SpectrumDirectory/server/bin/setup* script.
2. Run the *SpectrumDirectory/server/bin/server.stop* script to stop the Spectrum Technology Platform server.
3. Back up this file from *SpectrumDirectory* to a different location:

```
server/deploy/contextgraph-22.1.car
```
4. Use the link in the release announcement to download the ZIP file containing the product update. You can also find links to software, release notes, and checksum values on the [2022.1.0 Updates](#) page.
5. Extract the contents of the ZIP file to a temporary location.

6. FTP the `cdq20221s16.tar` file in binary mode to a temporary directory on the Spectrum Technology Platform machine.
7. Change to the directory where the Spectrum Technology Platform server is installed (*SpectrumDirectory*).
8. Untar the file using this command:

```
tar -xvzf TemporaryDirectory/cdq20221s16.tar
```
9. Run the *SpectrumDirectory/server/bin/server.start* script to start the Spectrum Technology Platform server.



1700 District Ave Ste 300
Burlington, MA 01803-5231
USA

www.precisely.com

Copyright 2007, 2023 Precisely